
Pillow (PIL Fork) Documentation

Release 7.1.2

Alex Clark

Jun 01, 2020

Contents

1	Installation	3
1.1	Warnings	3
1.2	Notes	3
1.3	Basic Installation	4
1.4	Building From Source	5
1.5	Platform Support	8
1.6	Old Versions	10
2	Handbook	11
2.1	Overview	11
2.2	Tutorial	12
2.3	Concepts	19
2.4	Appendices	22
3	Reference	47
3.1	Image Module	47
3.2	ImageChops (“Channel Operations”) Module	63
3.3	ImageColor Module	66
3.4	ImageCms Module	67
3.5	ImageDraw Module	81
3.6	ImageEnhance Module	88
3.7	ImageFile Module	89
3.8	ImageFilter Module	91
3.9	ImageFont Module	94
3.10	ImageGrab Module (macOS and Windows only)	99
3.11	ImageMath Module	100
3.12	ImageMorph Module	102
3.13	ImageOps Module	103
3.14	ImagePalette Module	106
3.15	ImagePath Module	107
3.16	ImageQt Module	108
3.17	ImageSequence Module	108
3.18	ImageStat Module	109
3.19	ImageTk Module	110
3.20	ImageWin Module (Windows-only)	111
3.21	ExifTags Module	112
3.22	TiffTags Module	113

3.23	PSDraw Module	113
3.24	PixelAccess Class	114
3.25	PyAccess Module	115
3.26	PIL Package (autodoc of remaining modules)	116
3.27	Plugin reference	124
3.28	Internal Reference Docs	143
4	Porting	147
5	About	149
5.1	Goals	149
5.2	License	149
5.3	Why a fork?	149
5.4	What about PIL?	149
6	Release Notes	151
6.1	7.1.2	151
6.2	7.1.1	151
6.3	7.1.0	152
6.4	7.0.0	153
6.5	6.2.2	156
6.6	6.2.1	156
6.7	6.2.0	157
6.8	6.1.0	158
6.9	6.0.0	160
6.10	5.4.1	164
6.11	5.4.0	165
6.12	5.3.0	166
6.13	5.2.0	167
6.14	5.1.0	169
6.15	5.0.0	169
6.16	4.3.0	171
6.17	4.2.1	173
6.18	4.2.0	173
6.19	4.1.1	174
6.20	4.1.0	174
6.21	4.0.0	176
6.22	3.4.0	176
6.23	3.3.2	177
6.24	3.3.0	178
6.25	3.2.0	178
6.26	3.1.2	179
6.27	3.1.1	180
6.28	3.1.0	181
6.29	3.0.0	182
6.30	2.8.0	183
6.31	2.7.0	183
7	Deprecations and removals	187
7.1	Deprecated features	187
7.2	Removed features	188
8	Indices and tables	191
	Python Module Index	193

Pillow is the friendly PIL fork by [Alex Clark and Contributors](#). PIL is the Python Imaging Library by Fredrik Lundh and Contributors.

Pillow for enterprise is available via the Tidelift Subscription. [Learn more](#).

1.1 Warnings

Warning: Pillow and PIL cannot co-exist in the same environment. Before installing Pillow, please uninstall PIL.

Warning: Pillow \geq 1.0 no longer supports “import Image”. Please use “from PIL import Image” instead.

Warning: Pillow \geq 2.1.0 no longer supports “import _imaging”. Please use “from PIL.Image import core as _imaging” instead.

1.2 Notes

Note: Pillow is supported on the following Python versions

Python	3.8	3.7	3.6	3.5	3.4	3.3	3.2	2.7	2.6	2.5	2.4
Pillow \geq 7	Yes	Yes	Yes	Yes							
Pillow 6.2.1 - 6.2.2	Yes	Yes	Yes	Yes				Yes			
Pillow 6.0 - 6.2.0		Yes	Yes	Yes				Yes			
Pillow 5.2 - 5.4		Yes	Yes	Yes	Yes			Yes			
Pillow 5.0 - 5.1			Yes	Yes	Yes			Yes			
Pillow 4			Yes	Yes	Yes	Yes		Yes			
Pillow 2 - 3				Yes	Yes	Yes	Yes	Yes	Yes		
Pillow $<$ 2								Yes	Yes	Yes	Yes

1.3 Basic Installation

Note: The following instructions will install Pillow with support for most common image formats. See [External Libraries](#) for a full list of external libraries supported.

Install Pillow with **pip**:

```
python3 -m pip install --upgrade pip
python3 -m pip install --upgrade Pillow
```

1.3.1 Windows Installation

We provide Pillow binaries for Windows compiled for the matrix of supported Pythons in both 32 and 64-bit versions in the wheel format. These binaries have all of the optional libraries included except for raqm, libimagequant, and libxcb:

```
python3 -m pip install --upgrade pip
python3 -m pip install --upgrade Pillow
```

1.3.2 macOS Installation

We provide binaries for macOS for each of the supported Python versions in the wheel format. These include support for all optional libraries except libimagequant and libxcb. Raqm support requires libraqm, fridibi, and harfbuzz to be installed separately:

```
python3 -m pip install --upgrade pip
python3 -m pip install --upgrade Pillow
```

1.3.3 Linux Installation

We provide binaries for Linux for each of the supported Python versions in the manylinux wheel format. These include support for all optional libraries except libimagequant. Raqm support requires libraqm, fridibi, and harfbuzz to be installed separately:

```
python3 -m pip install --upgrade pip
python3 -m pip install --upgrade Pillow
```

Most major Linux distributions, including Fedora, Debian/Ubuntu and ArchLinux also include Pillow in packages that previously contained PIL e.g. `python-imaging`.

1.3.4 FreeBSD Installation

Pillow can be installed on FreeBSD via the official Ports or Packages systems:

Ports:

```
cd /usr/ports/graphics/py-pillow && make install clean
```

Packages:

```
pkg install py36-pillow
```

Note: The [Pillow FreeBSD port](#) and packages are tested by the ports team with all supported FreeBSD versions.

1.4 Building From Source

Download and extract the [compressed archive](#) from PyPI.

1.4.1 External Libraries

Note: You **do not need to install all supported external libraries** to use Pillow's basic features. **Zlib** and **libjpeg** are required by default.

Note: There are Dockerfiles in our [Docker images repo](#) to install the dependencies for some operating systems.

Many of Pillow's features require external libraries:

- **libjpeg** provides JPEG functionality.
 - Pillow has been tested with libjpeg versions **6b**, **8**, **9-9d** and libjpeg-turbo version **8**.
 - Starting with Pillow 3.0.0, libjpeg is required by default, but may be disabled with the `--disable-jpeg` flag.
- **zlib** provides access to compressed PNGs
 - Starting with Pillow 3.0.0, zlib is required by default, but may be disabled with the `--disable-zlib` flag.
- **libtiff** provides compressed TIFF functionality
 - Pillow has been tested with libtiff versions **3.x** and **4.0-4.1**
- **libfreetype** provides type related services
- **littlecms** provides color management
 - Pillow version 2.2.1 and below uses liblcms1, Pillow 2.3.0 and above uses liblcms2. Tested with **1.19** and **2.7-2.9**.
- **libwebp** provides the WebP format.
 - Pillow has been tested with version **0.1.3**, which does not read transparent WebP files. Versions **0.3.0** and above support transparency.
- **tcl/tk** provides support for tkinter bitmap and photo images.
- **openjpeg** provides JPEG 2000 functionality.
 - Pillow has been tested with openjpeg **2.0.0**, **2.1.0** and **2.3.1**.
 - Pillow does **not** support the earlier **1.5** series which ships with Debian Jessie.
- **libimagequant** provides improved color quantization

- Pillow has been tested with libimagequant **2.6-2.12.6**
- Libimagequant is licensed GPLv3, which is more restrictive than the Pillow license, therefore we will not be distributing binaries with libimagequant support enabled.
- **libraqm** provides complex text layout support.
 - libraqm provides bidirectional text support (using FriBiDi), shaping (using HarfBuzz), and proper script itemization. As a result, Raqm can support most writing systems covered by Unicode.
 - libraqm depends on the following libraries: FreeType, HarfBuzz, FriBiDi, make sure that you install them before installing libraqm if not available as package in your system.
 - setting text direction or font features is not supported without libraqm.
 - libraqm is dynamically loaded in Pillow 5.0.0 and above, so support is available if all the libraries are installed.
 - Windows support: Raqm is not included in prebuilt wheels
- **libxcb** provides X11 screengrab support.

Once you have installed the prerequisites, run:

```
python3 -m pip install --upgrade pip
python3 -m pip install --upgrade Pillow
```

If the prerequisites are installed in the standard library locations for your machine (e.g. /usr or /usr/local), no additional configuration should be required. If they are installed in a non-standard location, you may need to configure setuptools to use those locations by editing `setup.py` or `setup.cfg`, or by adding environment variables on the command line:

```
CFLAGS="-I/usr/pkg/include" python3 -m pip install --upgrade Pillow
```

If Pillow has been previously built without the required prerequisites, it may be necessary to manually clear the pip cache or build without cache using the `--no-cache-dir` option to force a build with newly installed external libraries.

1.4.2 Build Options

- **Environment variable:** `MAX_CONCURRENCY=n`. Pillow can use multiprocessing to build the extension. Setting `MAX_CONCURRENCY` sets the number of CPUs to use, or can disable parallel building by using a setting of 1. By default, it uses 4 CPUs, or if 4 are not available, as many as are present.
- **Build flags:** `--disable-zlib`, `--disable-jpeg`, `--disable-tiff`, `--disable-freetype`, `--disable-lcms`, `--disable-webp`, `--disable-webpmux`, `--disable-jpeg2000`, `--disable-imagequant`, `--disable-xcb`. Disable building the corresponding feature even if the development libraries are present on the building machine.
- **Build flags:** `--enable-zlib`, `--enable-jpeg`, `--enable-tiff`, `--enable-freetype`, `--enable-lcms`, `--enable-webp`, `--enable-webpmux`, `--enable-jpeg2000`, `--enable-imagequant`, `--enable-xcb`. Require that the corresponding feature is built. The build will raise an exception if the libraries are not found. Webpmux (WebP metadata) relies on WebP support. Tcl and Tk also must be used together.
- **Build flag:** `--disable-platform-guessing`. Skips all of the platform dependent guessing of include and library directories for automated build systems that configure the proper paths in the environment variables (e.g. Buildroot).

- **Build flag:** `--debug`. Adds a debugging flag to the include and library search process to dump all paths searched for and found to stdout.

Sample usage:

```
MAX_CONCURRENCY=1 python3 setup.py build_ext --enable-[feature] install
```

or using pip:

```
python3 -m pip install --upgrade Pillow --global-option="build_ext" --global-option="-<br>↪-enable-[feature]"
```

1.4.3 Building on macOS

The Xcode command line tools are required to compile portions of Pillow. The tools are installed by running `xcode-select --install` from the command line. The command line tools are required even if you have the full Xcode package installed. It may be necessary to run `sudo xcodebuild -license` to accept the license prior to using the tools.

The easiest way to install external libraries is via [Homebrew](#). After you install Homebrew, run:

```
brew install libtiff libjpeg webp little-cms2
```

To install `libraqm` on macOS use Homebrew to install its dependencies:

```
brew install freetype harfbuzz fribidi
```

Then see `depends/install_raqm_cmake.sh` to install `libraqm`.

Now install Pillow with:

```
python3 -m pip install --upgrade pip
python3 -m pip install --upgrade Pillow
```

or from within the uncompressed source directory:

```
python3 setup.py install
```

1.4.4 Building on Windows

We don't recommend trying to build on Windows. It is a maze of twisty passages, mostly dead ends. There are build scripts and notes for the Windows build in the `winbuild` directory.

1.4.5 Building on FreeBSD

Note: Only FreeBSD 10 and 11 tested

Make sure you have Python's development libraries installed:

```
sudo pkg install python3
```

Prerequisites are installed on **FreeBSD 10 or 11** with:

```
sudo pkg install jpeg-turbo tiff webp lcms2 freetype2 openjpeg harfbuzz fribidi libxcb
```

Then see `depends/install_raqm_cmake.sh` to install `libraqm`.

1.4.6 Building on Linux

If you didn't build Python from source, make sure you have Python's development libraries installed.

In Debian or Ubuntu:

```
sudo apt-get install python3-dev python3-setuptools
```

In Fedora, the command is:

```
sudo dnf install python3-devel redhat-rpm-config
```

Note: `redhat-rpm-config` is required on Fedora 23, but not earlier versions.

Prerequisites are installed on **Ubuntu 16.04 LTS** with:

```
sudo apt-get install libtiff5-dev libjpeg8-dev libopenjp2-7-dev zlib1g-dev \  
libfreetype6-dev liblcms2-dev libwebp-dev tcl8.6-dev tk8.6-dev python3-tk \  
libharfbuzz-dev libfribidi-dev libxcb1-dev
```

Then see `depends/install_raqm.sh` to install `libraqm`.

Prerequisites are installed on recent **RedHat Centos** or **Fedora** with:

```
sudo dnf install libtiff-devel libjpeg-devel openjpeg2-devel zlib-devel \  
freetype-devel lcms2-devel libwebp-devel tcl-devel tk-devel \  
harfbuzz-devel fribidi-devel libraqm-devel libimagequant-devel libxcb-devel
```

Note that the package manager may be `yum` or `dnf`, depending on the exact distribution.

See also the `Dockerfiles` in the Test Infrastructure repo (<https://github.com/python-pillow/docker-images>) for a known working install process for other tested distros.

1.4.7 Building on Android

Basic Android support has been added for compilation within the Termux environment. The dependencies can be installed by:

```
pkg install -y python ndk-sysroot clang make \  
libjpeg-turbo
```

This has been tested within the Termux app on ChromeOS, on x86.

1.5 Platform Support

Current platform support for Pillow. Binary distributions are contributed for each release on a volunteer basis, but the source should compile and run everywhere platform support is listed. In general, we aim to support all current versions of Linux, macOS, and Windows.

1.5.1 Continuous Integration Targets

These platforms are built and tested for every change.

Operating system	Tested Python versions	Tested architecture
Alpine	3.8	x86-64
Arch	3.8	x86-64
Amazon Linux 1	3.6	x86-64
Amazon Linux 2	3.7	x86-64
CentOS 6	3.6	x86-64
CentOS 7	3.6	x86-64
CentOS 8	3.6	x86-64
Debian 9 Stretch	3.5	x86
Debian 10 Buster	3.7	x86
Fedora 30	3.7	x86-64
Fedora 31	3.7	x86-64
macOS 10.15 Catalina	3.5, 3.6, 3.7, 3.8, PyPy3	x86-64
Ubuntu Linux 16.04 LTS	3.5, 3.6, 3.7, 3.8, PyPy3	x86-64
Windows Server 2012 R2	3.5, 3.8	x86, x86-64
	PyPy3, 3.7/MinGW	x86
Windows Server 2019	3.5, 3.6, 3.7, 3.8	x86, x86-64
	PyPy3	x86

1.5.2 Other Platforms

These platforms have been reported to work at the versions mentioned.

Note: Contributors please test Pillow on your platform then update this document and send a pull request.

Operating system	Tested Python versions	Latest tested Pillow version	Tested processors
macOS 10.15 Catalina	3.5, 3.6, 3.7, 3.8	7.0.0	x86-64
macOS 10.14 Mojave	2.7, 3.5, 3.6, 3.7	6.0.0	x86-64
	3.4	5.4.1	
macOS 10.13 High Sierra	2.7, 3.4, 3.5, 3.6	4.2.1	x86-64
macOS 10.12 Sierra	2.7, 3.4, 3.5, 3.6	4.1.1	x86-64
Mac OS X 10.11 El Capitan	2.7, 3.4, 3.5, 3.6, 3.7	5.4.1	x86-64
	3.3	4.1.0	
Mac OS X 10.9 Mavericks	2.7, 3.2, 3.3, 3.4	3.0.0	x86-64
Mac OS X 10.8 Mountain Lion	2.6, 2.7, 3.2, 3.3		x86-64
Redhat Linux 6	2.6		x86
CentOS 6.3	2.7, 3.3		x86
Fedora 23	2.7, 3.4	3.1.0	x86-64
Ubuntu Linux 12.04 LTS	2.6, 3.2, 3.3, 3.4, 3.5 PyPy5.3.1, PyPy3 v2.4.0	3.4.1	x86,x86-64
	2.7	4.3.0	x86-64
	2.7, 3.2	3.4.1	ppc
Ubuntu Linux 10.04 LTS	2.6	2.3.0	x86,x86-64
Debian 8.2 Jessie	2.7, 3.4	3.1.0	x86-64
Raspbian Jessie	2.7, 3.4	3.1.0	arm
Raspbian Stretch	2.7, 3.5	4.0.0	arm
Gentoo Linux	2.7, 3.2	2.1.0	x86-64
FreeBSD 11.1	2.7, 3.4, 3.5, 3.6	4.3.0	x86-64
FreeBSD 10.3	2.7, 3.4, 3.5	4.2.0	x86-64
FreeBSD 10.2	2.7, 3.4	3.1.0	x86-64
Windows 8.1 Pro	2.6, 2.7, 3.2, 3.3, 3.4	2.4.0	x86,x86-64
Windows 8 Pro	2.6, 2.7, 3.2, 3.3, 3.4a3	2.2.0	x86,x86-64
Windows 7 Pro	2.7, 3.2, 3.3	3.4.1	x86-64
Windows Server 2008 R2 Enterprise	3.3		x86-64

1.6 Old Versions

You can download old distributions from the [release history](#) at PyPI and by direct URL access eg. <https://pypi.org/project/Pillow/1.0/>.

2.1 Overview

The **Python Imaging Library** adds image processing capabilities to your Python interpreter.

This library provides extensive file format support, an efficient internal representation, and fairly powerful image processing capabilities.

The core image library is designed for fast access to data stored in a few basic pixel formats. It should provide a solid foundation for a general image processing tool.

Let's look at a few possible uses of this library.

2.1.1 Image Archives

The Python Imaging Library is ideal for image archival and batch processing applications. You can use the library to create thumbnails, convert between file formats, print images, etc.

The current version identifies and reads a large number of formats. Write support is intentionally restricted to the most commonly used interchange and presentation formats.

2.1.2 Image Display

The current release includes Tk *PhotoImage* and *BitmapImage* interfaces, as well as a *Windows DIB interface* that can be used with PythonWin and other Windows-based toolkits. Many other GUI toolkits come with some kind of PIL support.

For debugging, there's also a *show()* method which saves an image to disk, and calls an external display utility.

2.1.3 Image Processing

The library contains basic image processing functionality, including point operations, filtering with a set of built-in convolution kernels, and colour space conversions.

The library also supports image resizing, rotation and arbitrary affine transforms.

There's a histogram method allowing you to pull some statistics out of an image. This can be used for automatic contrast enhancement, and for global statistical analysis.

2.2 Tutorial

2.2.1 Using the Image class

The most important class in the Python Imaging Library is the *Image* class, defined in the module with the same name. You can create instances of this class in several ways; either by loading images from files, processing other images, or creating images from scratch.

To load an image from a file, use the *open()* function in the *Image* module:

```
>>> from PIL import Image
>>> im = Image.open("hopper.ppm")
```

If successful, this function returns an *Image* object. You can now use instance attributes to examine the file contents:

```
>>> print(im.format, im.size, im.mode)
PPM (512, 512) RGB
```

The *format* attribute identifies the source of an image. If the image was not read from a file, it is set to *None*. The *size* attribute is a 2-tuple containing width and height (in pixels). The *mode* attribute defines the number and names of the bands in the image, and also the pixel type and depth. Common modes are "L" (luminance) for greyscale images, "RGB" for true color images, and "CMYK" for pre-press images.

If the file cannot be opened, an *IOError* exception is raised.

Once you have an instance of the *Image* class, you can use the methods defined by this class to process and manipulate the image. For example, let's display the image we just loaded:

```
>>> im.show()
```

Note: The standard version of *show()* is not very efficient, since it saves the image to a temporary file and calls a utility to display the image. If you don't have an appropriate utility installed, it won't even work. When it does work though, it is very handy for debugging and tests.

The following sections provide an overview of the different functions provided in this library.

2.2.2 Reading and writing images

The Python Imaging Library supports a wide variety of image file formats. To read files from disk, use the *open()* function in the *Image* module. You don't have to know the file format to open a file. The library automatically determines the format based on the contents of the file.

To save a file, use the *save()* method of the *Image* class. When saving files, the name becomes important. Unless you specify the format, the library uses the filename extension to discover which file storage format to use.

Convert files to JPEG

```
import os, sys
from PIL import Image

for infile in sys.argv[1:]:
    f, e = os.path.splitext(infile)
    outfile = f + ".jpg"
    if infile != outfile:
        try:
            with Image.open(infile) as im:
                im.save(outfile)
        except IOError:
            print("cannot convert", infile)
```

A second argument can be supplied to the `save()` method which explicitly specifies a file format. If you use a non-standard extension, you must always specify the format this way:

Create JPEG thumbnails

```
import os, sys
from PIL import Image

size = (128, 128)

for infile in sys.argv[1:]:
    outfile = os.path.splitext(infile)[0] + ".thumbnail"
    if infile != outfile:
        try:
            with Image.open(infile) as im:
                im.thumbnail(size)
                im.save(outfile, "JPEG")
        except IOError:
            print("cannot create thumbnail for", infile)
```

It is important to note that the library doesn't decode or load the raster data unless it really has to. When you open a file, the file header is read to determine the file format and extract things like mode, size, and other properties required to decode the file, but the rest of the file is not processed until later.

This means that opening an image file is a fast operation, which is independent of the file size and compression type. Here's a simple script to quickly identify a set of image files:

Identify Image Files

```
import sys
from PIL import Image

for infile in sys.argv[1:]:
    try:
        with Image.open(infile) as im:
            print(infile, im.format, "%dx%d" % im.size, im.mode)
    except IOError:
        pass
```

2.2.3 Cutting, pasting, and merging images

The *Image* class contains methods allowing you to manipulate regions within an image. To extract a sub-rectangle from an image, use the *crop()* method.

Copying a subrectangle from an image

```
box = (100, 100, 400, 400)
region = im.crop(box)
```

The region is defined by a 4-tuple, where coordinates are (left, upper, right, lower). The Python Imaging Library uses a coordinate system with (0, 0) in the upper left corner. Also note that coordinates refer to positions between the pixels, so the region in the above example is exactly 300x300 pixels.

The region could now be processed in a certain manner and pasted back.

Processing a subrectangle, and pasting it back

```
region = region.transpose(Image.ROTATE_180)
im.paste(region, box)
```

When pasting regions back, the size of the region must match the given region exactly. In addition, the region cannot extend outside the image. However, the modes of the original image and the region do not need to match. If they don't, the region is automatically converted before being pasted (see the section on *Color transforms* below for details).

Here's an additional example:

Rolling an image

```
def roll(image, delta):
    """Roll an image sideways."""
    xsize, ysize = image.size

    delta = delta % xsize
    if delta == 0: return image

    part1 = image.crop((0, 0, delta, ysize))
    part2 = image.crop((delta, 0, xsize, ysize))
    image.paste(part1, (xsize-delta, 0, xsize, ysize))
    image.paste(part2, (0, 0, xsize-delta, ysize))

    return image
```

For more advanced tricks, the paste method can also take a transparency mask as an optional argument. In this mask, the value 255 indicates that the pasted image is opaque in that position (that is, the pasted image should be used as is). The value 0 means that the pasted image is completely transparent. Values in-between indicate different levels of transparency. For example, pasting an RGBA image and also using it as the mask would paste the opaque portion of the image but not its transparent background.

The Python Imaging Library also allows you to work with the individual bands of a multi-band image, such as an RGB image. The split method creates a set of new images, each containing one band from the original multi-band image. The merge function takes a mode and a tuple of images, and combines them into a new image. The following sample swaps the three bands of an RGB image:

Splitting and merging bands

```
r, g, b = im.split()
im = Image.merge("RGB", (b, g, r))
```

Note that for a single-band image, `split()` returns the image itself. To work with individual color bands, you may want to convert the image to “RGB” first.

2.2.4 Geometrical transforms

The `PIL.Image.Image` class contains methods to `resize()` and `rotate()` an image. The former takes a tuple giving the new size, the latter the angle in degrees counter-clockwise.

Simple geometry transforms

```
out = im.resize((128, 128))
out = im.rotate(45) # degrees counter-clockwise
```

To rotate the image in 90 degree steps, you can either use the `rotate()` method or the `transpose()` method. The latter can also be used to flip an image around its horizontal or vertical axis.

Transposing an image

```
out = im.transpose(Image.FLIP_LEFT_RIGHT)
out = im.transpose(Image.FLIP_TOP_BOTTOM)
out = im.transpose(Image.ROTATE_90)
out = im.transpose(Image.ROTATE_180)
out = im.transpose(Image.ROTATE_270)
```

`transpose(ROTATE)` operations can also be performed identically with `rotate()` operations, provided the `expand` flag is true, to provide for the same changes to the image’s size.

A more general form of image transformations can be carried out via the `transform()` method.

2.2.5 Color transforms

The Python Imaging Library allows you to convert images between different pixel representations using the `convert()` method.

Converting between modes

```
from PIL import Image
with Image.open("hopper.ppm") as im:
    im = im.convert("L")
```

The library supports transformations between each supported mode and the “L” and “RGB” modes. To convert between other modes, you may have to use an intermediate image (typically an “RGB” image).

2.2.6 Image enhancement

The Python Imaging Library provides a number of methods and modules that can be used to enhance images.

Filters

The `ImageFilter` module contains a number of pre-defined enhancement filters that can be used with the `filter()` method.

Applying filters

```
from PIL import ImageFilter
out = im.filter(ImageFilter.DETAIL)
```

Point Operations

The `point()` method can be used to translate the pixel values of an image (e.g. image contrast manipulation). In most cases, a function object expecting one argument can be passed to this method. Each pixel is processed according to that function:

Applying point transforms

```
# multiply each pixel by 1.2
out = im.point(lambda i: i * 1.2)
```

Using the above technique, you can quickly apply any simple expression to an image. You can also combine the `point()` and `paste()` methods to selectively modify an image:

Processing individual bands

```
# split the image into individual bands
source = im.split()

R, G, B = 0, 1, 2

# select regions where red is less than 100
mask = source[R].point(lambda i: i < 100 and 255)

# process the green band
out = source[G].point(lambda i: i * 0.7)

# paste the processed band back, but only where red was < 100
source[G].paste(out, None, mask)

# build a new multiband image
im = Image.merge(im.mode, source)
```

Note the syntax used to create the mask:

```
imout = im.point(lambda i: expression and 255)
```

Python only evaluates the portion of a logical expression as is necessary to determine the outcome, and returns the last value examined as the result of the expression. So if the expression above is false (0), Python does not look at the second operand, and thus returns 0. Otherwise, it returns 255.

Enhancement

For more advanced image enhancement, you can use the classes in the *ImageEnhance* module. Once created from an image, an enhancement object can be used to quickly try out different settings.

You can adjust contrast, brightness, color balance and sharpness in this way.

Enhancing images

```
from PIL import ImageEnhance

enh = ImageEnhance.Contrast(im)
enh.enhance(1.3).show("30% more contrast")
```

2.2.7 Image sequences

The Python Imaging Library contains some basic support for image sequences (also called animation formats). Supported sequence formats include FLI/FLC, GIF, and a few experimental formats. TIFF files can also contain more than one frame.

When you open a sequence file, PIL automatically loads the first frame in the sequence. You can use the seek and tell methods to move between different frames:

Reading sequences

```
from PIL import Image

with Image.open("animation.gif") as im:
    im.seek(1) # skip to the second frame

    try:
        while 1:
            im.seek(im.tell()+1)
            # do something to im
    except EOFError:
        pass # end of sequence
```

As seen in this example, you'll get an EOFError exception when the sequence ends.

The following class lets you use the for-statement to loop over the sequence:

Using the ImageSequence Iterator class

```
from PIL import ImageSequence
for frame in ImageSequence.Iterator(im):
    # ...do something to frame...
```

2.2.8 Postscript printing

The Python Imaging Library includes functions to print images, text and graphics on Postscript printers. Here's a simple example:

Drawing Postscript

```
from PIL import Image
from PIL import PSDraw

with Image.open("hopper.ppm") as im:
    title = "hopper"
    box = (1*72, 2*72, 7*72, 10*72) # in points

    ps = PSDraw.PSDraw() # default is sys.stdout
    ps.begin_document(title)

    # draw the image (75 dpi)
    ps.image(box, im, 75)
    ps.rectangle(box)

    # draw title
    ps.setfont("HelveticaNarrow-Bold", 36)
    ps.text((3*72, 4*72), title)

    ps.end_document()
```

2.2.9 More on reading images

As described earlier, the `open()` function of the `Image` module is used to open an image file. In most cases, you simply pass it the filename as an argument. `Image.open()` can be used as a context manager:

```
from PIL import Image
with Image.open("hopper.ppm") as im:
    ...
```

If everything goes well, the result is an `PIL.Image.Image` object. Otherwise, an `IOError` exception is raised.

You can use a file-like object instead of the filename. The object must implement `read()`, `seek()` and `tell()` methods, and be opened in binary mode.

Reading from an open file

```
from PIL import Image
with open("hopper.ppm", "rb") as fp:
    im = Image.open(fp)
```

To read an image from binary data, use the `BytesIO` class:

Reading from binary data

```
from PIL import Image
import io
im = Image.open(io.BytesIO(buffer))
```

Note that the library rewinds the file (using `seek(0)`) before reading the image header. In addition, `seek` will also be used when the image data is read (by the `load` method). If the image file is embedded in a larger file, such as a tar file, you can use the `ContainerIO` or `TarIO` modules to access it.

Reading from a tar archive

```
from PIL import Image, TarIO

fp = TarIO.TarIO("Tests/images/hopper.tar", "hopper.jpg")
im = Image.open(fp)
```

2.2.10 Controlling the decoder

Some decoders allow you to manipulate the image while reading it from a file. This can often be used to speed up decoding when creating thumbnails (when speed is usually more important than quality) and printing to a monochrome laser printer (when only a greyscale version of the image is needed).

The `draft()` method manipulates an opened but not yet loaded image so it as closely as possible matches the given mode and size. This is done by reconfiguring the image decoder.

Reading in draft mode

This is only available for JPEG and MPO files.

```
from PIL import Image

with Image.open(file) as im:
    print("original =", im.mode, im.size)

    im.draft("L", (100, 100))
    print("draft =", im.mode, im.size)
```

This prints something like:

```
original = RGB (512, 512)
draft = L (128, 128)
```

Note that the resulting image may not exactly match the requested mode and size. To make sure that the image is not larger than the given size, use the `thumbnail` method instead.

2.3 Concepts

The Python Imaging Library handles *raster images*; that is, rectangles of pixel data.

2.3.1 Bands

An image can consist of one or more bands of data. The Python Imaging Library allows you to store several bands in a single image, provided they all have the same dimensions and depth. For example, a PNG image might have ‘R’, ‘G’, ‘B’, and ‘A’ bands for the red, green, blue, and alpha transparency values. Many operations act on each band separately, e.g., histograms. It is often useful to think of each pixel as having one value per band.

To get the number and names of bands in an image, use the `getbands()` method.

2.3.2 Modes

The `mode` of an image defines the type and depth of a pixel in the image. Each pixel uses the full range of the bit depth. So a 1-bit pixel has a range of 0-1, an 8-bit pixel has a range of 0-255 and so on. The current release supports the following standard modes:

- 1 (1-bit pixels, black and white, stored with one pixel per byte)
- L (8-bit pixels, black and white)
- P (8-bit pixels, mapped to any other mode using a color palette)
- RGB (3x8-bit pixels, true color)
- RGBA (4x8-bit pixels, true color with transparency mask)
- CMYK (4x8-bit pixels, color separation)
- YCbCr (3x8-bit pixels, color video format)
 - Note that this refers to the JPEG, and not the ITU-R BT.2020, standard
- LAB (3x8-bit pixels, the L*a*b color space)
- HSV (3x8-bit pixels, Hue, Saturation, Value color space)
- I (32-bit signed integer pixels)
- F (32-bit floating point pixels)

Pillow also provides limited support for a few special modes, including:

- LA (L with alpha)
- PA (P with alpha)
- RGBX (true color with padding)
- RGBa (true color with premultiplied alpha)
- La (L with premultiplied alpha)
- I;16 (16-bit unsigned integer pixels)
- I;16L (16-bit little endian unsigned integer pixels)
- I;16B (16-bit big endian unsigned integer pixels)
- I;16N (16-bit native endian unsigned integer pixels)
- BGR;15 (15-bit reversed true colour)
- BGR;16 (16-bit reversed true colour)
- BGR;24 (24-bit reversed true colour)
- BGR;32 (32-bit reversed true colour)

However, Pillow doesn't support user-defined modes; if you need to handle band combinations that are not listed above, use a sequence of Image objects.

You can read the mode of an image through the `mode` attribute. This is a string containing one of the above values.

2.3.3 Size

You can read the image size through the `size` attribute. This is a 2-tuple, containing the horizontal and vertical size in pixels.

2.3.4 Coordinate System

The Python Imaging Library uses a Cartesian pixel coordinate system, with (0,0) in the upper left corner. Note that the coordinates refer to the implied pixel corners; the centre of a pixel addressed as (0, 0) actually lies at (0.5, 0.5).

Coordinates are usually passed to the library as 2-tuples (x, y). Rectangles are represented as 4-tuples, with the upper left corner given first. For example, a rectangle covering all of an 800x600 pixel image is written as (0, 0, 800, 600).

2.3.5 Palette

The palette mode (P) uses a color palette to define the actual color for each pixel.

2.3.6 Info

You can attach auxiliary information to an image using the `info` attribute. This is a dictionary object.

How such information is handled when loading and saving image files is up to the file format handler (see the chapter on *Image file formats*). Most handlers add properties to the `info` attribute when loading an image, but ignore it when saving images.

2.3.7 Orientation

A common element of the `info` attribute for JPG and TIFF images is the EXIF orientation tag. This is an instruction for how the image data should be oriented. For example, it may instruct an image to be rotated by 90 degrees, or to be mirrored. To apply this information to an image, `exif_transpose()` can be used.

2.3.8 Filters

For geometry operations that may map multiple input pixels to a single output pixel, the Python Imaging Library provides different resampling *filters*.

NEAREST Pick one nearest pixel from the input image. Ignore all other input pixels.

BOX Each pixel of source image contributes to one pixel of the destination image with identical weights. For upscaling is equivalent of NEAREST. This filter can only be used with the `resize()` and `thumbnail()` methods.

New in version 3.4.0.

BILINEAR For `resize` calculate the output pixel value using linear interpolation on all pixels that may contribute to the output value. For other transformations linear interpolation over a 2x2 environment in the input image is used.

HAMMING Produces a sharper image than `BILINEAR`, doesn't have dislocations on local level like with `BOX`. This filter can only be used with the `resize()` and `thumbnail()` methods.

New in version 3.4.0.

BICUBIC For `resize` calculate the output pixel value using cubic interpolation on all pixels that may contribute to the output value. For other transformations cubic interpolation over a 4x4 environment in the input image is used.

LANCZOS Calculate the output pixel value using a high-quality Lanczos filter (a truncated sinc) on all pixels that may contribute to the output value. This filter can only be used with the `resize()` and `thumbnail()` methods.

New in version 1.1.3.

Filters comparison table

Filter	Downscaling quality	Upscaling quality	Performance
NEAREST			
BOX			
BILINEAR			
HAMMING			
BICUBIC			
LANCZOS			

2.4 Appendices

Note: Contributors please include appendices as needed or appropriate with your bug fixes, feature additions and tests.

2.4.1 Image file formats

The Python Imaging Library supports a wide variety of raster file formats. Over 30 different file formats can be identified and read by the library. Write support is less extensive, but most common interchange and presentation formats are supported.

The `open()` function identifies files from their contents, not their names, but the `save()` method looks at the name to determine which format to use, unless the format is given explicitly.

Fully supported formats

Contents

- *Image file formats*
 - *Fully supported formats*
 - * *BMP*
 - * *DIB*
 - * *EPS*

- * *GIF*
 - *Reading sequences*
 - *Saving*
 - *Reading local images*
- * *ICNS*
- * *ICO*
- * *IM*
- * *JPEG*
- * *JPEG 2000*
- * *MSP*
- * *PCX*
- * *PNG*
 - *APNG sequences*
 - *Saving*
- * *PPM*
- * *SGI*
- * *SPIDER*
 - *Writing files in SPIDER format*
- * *TGA*
- * *TIFF*
 - *Reading Multi-frame TIFF Images*
 - *Saving Tiff Images*
- * *WebP*
 - *Saving sequences*
- * *XBM*
- *Read-only formats*
 - * *BLP*
 - * *CUR*
 - * *DCX*
 - * *DDS*
 - * *FLI, FLC*
 - * *FPX*
 - * *FTEX*
 - * *GBR*
 - * *GD*

- * *IMT*
- * *IPTC/NAA*
- * *MCIDAS*
- * *MIC*
- * *MPO*
- * *PCD*
- * *PIXAR*
- * *PSD*
- * *WAL*
- * *WMF*
- * *XPM*
- *Write-only formats*
 - * *PALM*
 - * *PDF*
 - * *XV Thumbnails*
- *Identify-only formats*
 - * *BUFR*
 - * *FITS*
 - * *GRIB*
 - * *HDF5*
 - * *MPEG*

BMP

Pillow reads and writes Windows and OS/2 BMP files containing 1, L, P, or RGB data. 16-colour images are read as P images. Run-length encoding is not supported.

The `open()` method sets the following `info` properties:

compression Set to `bmp_rle` if the file is run-length encoded.

DIB

Pillow reads and writes DIB files. DIB files are similar to BMP files, so see above for more information.

New in version 6.0.0.

EPS

Pillow identifies EPS files containing image data, and can read files that contain embedded raster images (ImageData descriptors). If Ghostscript is available, other EPS files can be read as well. The EPS driver can also write EPS images. The EPS driver can read EPS images in L, LAB, RGB and CMYK mode, but Ghostscript may convert the images to

RGB mode rather than leaving them in the original color space. The EPS driver can write images in L, RGB and CMYK modes.

If Ghostscript is available, you can call the `load()` method with the following parameter to affect how Ghostscript renders the EPS

scale Affects the scale of the resultant rasterized image. If the EPS suggests that the image be rendered at 100px x 100px, setting this parameter to 2 will make the Ghostscript render a 200px x 200px image instead. The relative position of the bounding box is maintained:

```
im = Image.open(...)
im.size # (100, 100)
im.load(scale=2)
im.size # (200, 200)
```

GIF

Pillow reads GIF87a and GIF89a versions of the GIF file format. The library writes run-length encoded files in GIF87a by default, unless GIF89a features are used or GIF89a is already in use.

Note that GIF files are always read as grayscale (L) or palette mode (P) images.

The `open()` method sets the following `info` properties:

background Default background color (a palette color index).

transparency Transparency color index. This key is omitted if the image is not transparent.

version Version (either GIF87a or GIF89a).

duration May not be present. The time to display the current frame of the GIF, in milliseconds.

loop May not be present. The number of times the GIF should loop. 0 means that it will loop forever.

comment May not be present. A comment about the image.

extension May not be present. Contains application specific information.

Reading sequences

The GIF loader supports the `seek()` and `tell()` methods. You can combine these methods to seek to the next frame (`im.seek(im.tell() + 1)`).

`im.seek()` raises an `EOFError` if you try to seek after the last frame.

Saving

When calling `save()` to write a GIF file, the following options are available:

```
im.save(out, save_all=True, append_images=[im1, im2, ...])
```

save_all If present and true, all frames of the image will be saved. If not, then only the first frame of a multiframe image will be saved.

append_images A list of images to append as additional frames. Each of the images in the list can be single or multiframe images. This is currently supported for GIF, PDF, TIFF, and WebP.

It is also supported for ICNS. If images are passed in of relevant sizes, they will be used instead of scaling down the main image.

include_color_table Whether or not to include local color table.

interlace Whether or not the image is interlaced. By default, it is, unless the image is less than 16 pixels in width or height.

disposal Indicates the way in which the graphic is to be treated after being displayed.

- 0 - No disposal specified.
- 1 - Do not dispose.
- 2 - Restore to background color.
- 3 - Restore to previous content.

Pass a single integer for a constant disposal, or a list or tuple to set the disposal for each frame separately.

palette Use the specified palette for the saved image. The palette should be a bytes or bytearray object containing the palette entries in RGBRGB... form. It should be no more than 768 bytes. Alternately, the palette can be passed in as an `PIL.ImagePalette.ImagePalette` object.

optimize If present and true, attempt to compress the palette by eliminating unused colors. This is only useful if the palette can be compressed to the next smaller power of 2 elements.

Note that if the image you are saving comes from an existing GIF, it may have the following properties in its `info` dictionary. For these options, if you do not pass them in, they will default to their `info` values.

transparency Transparency color index.

duration The display duration of each frame of the multiframe gif, in milliseconds. Pass a single integer for a constant duration, or a list or tuple to set the duration for each frame separately.

loop Integer number of times the GIF should loop. 0 means that it will loop forever. By default, the image will not loop.

comment A comment about the image.

Reading local images

The GIF loader creates an image memory the same size as the GIF file's *logical screen size*, and pastes the actual pixel data (the *local image*) into this image. If you only want the actual pixel rectangle, you can manipulate the `size` and `tile` attributes before loading the file:

```
im = Image.open(...)

if im.tile[0][0] == "gif":
    # only read the first "local image" from this GIF file
    tag, (x0, y0, x1, y1), offset, extra = im.tile[0]
    im.size = (x1 - x0, y1 - y0)
    im.tile = [(tag, (0, 0) + im.size, offset, extra)]
```

ICNS

Pillow reads and (macOS only) writes macOS `.icns` files. By default, the largest available icon is read, though you can override this by setting the `size` property before calling `load()`. The `open()` method sets the following `info` property:

sizes A list of supported sizes found in this icon file; these are a 3-tuple, (*width*, *height*, *scale*), where *scale* is 2 for a retina icon and 1 for a standard icon. You *are* permitted to use this 3-tuple format for the *size* property if you set it before calling `load()`; after loading, the size will be reset to a 2-tuple containing pixel dimensions (so, e.g. if you ask for (512, 512, 2), the final value of *size* will be (1024, 1024)).

The `save()` method can take the following keyword arguments:

append_images A list of images to replace the scaled down versions of the image. The order of the images does not matter, as their use is determined by the size of each image.

New in version 5.1.0.

ICO

ICO is used to store icons on Windows. The largest available icon is read.

The `save()` method supports the following options:

sizes A list of sizes including in this ico file; these are a 2-tuple, (*width*, *height*); Default to [(16, 16), (24, 24), (32, 32), (48, 48), (64, 64), (128, 128), (256, 256)]. Any sizes bigger than the original size or 256 will be ignored.

IM

IM is a format used by LabEye and other applications based on the IFUNC image processing library. The library reads and writes most uncompressed interchange versions of this format.

IM is the only format that can store all internal Pillow formats.

JPEG

Pillow reads JPEG, JFIF, and Adobe JPEG files containing L, RGB, or CMYK data. It writes standard and progressive JFIF files.

Using the `draft()` method, you can speed things up by converting RGB images to L, and resize images to 1/2, 1/4 or 1/8 of their original size while loading them.

The `open()` method may set the following `info` properties if available:

jfif JFIF application marker found. If the file is not a JFIF file, this key is not present.

jfif_version A tuple representing the jfif version, (major version, minor version).

jfif_density A tuple representing the pixel density of the image, in units specified by `jfif_unit`.

jfif_unit Units for the `jfif_density`:

- 0 - No Units
- 1 - Pixels per Inch
- 2 - Pixels per Centimeter

dpi A tuple representing the reported pixel density in pixels per inch, if the file is a jfif file and the units are in inches.

adobe Adobe application marker found. If the file is not an Adobe JPEG file, this key is not present.

adobe_transform Vendor Specific Tag.

progression Indicates that this is a progressive JPEG file.

icc_profile The ICC color profile for the image.

exif Raw EXIF data from the image.

comment A comment about the image.

New in version 7.1.0.

The `save()` method supports the following options:

quality The image quality, on a scale from 0 (worst) to 95 (best). The default is 75. Values above 95 should be avoided; 100 disables portions of the JPEG compression algorithm, and results in large files with hardly any gain in image quality.

optimize If present and true, indicates that the encoder should make an extra pass over the image in order to select optimal encoder settings.

progressive If present and true, indicates that this image should be stored as a progressive JPEG file.

dpi A tuple of integers representing the pixel density, (x, y) .

icc_profile If present and true, the image is stored with the provided ICC profile. If this parameter is not provided, the image will be saved with no profile attached. To preserve the existing profile:

```
im.save(filename, 'jpeg', icc_profile=im.info.get('icc_profile'))
```

exif If present, the image will be stored with the provided raw EXIF data.

subsampling If present, sets the subsampling for the encoder.

- `keep`: Only valid for JPEG files, will retain the original image setting.
- `4:4:4, 4:2:2, 4:2:0`: Specific sampling values
- `-1`: equivalent to `keep`
- `0`: equivalent to `4:4:4`
- `1`: equivalent to `4:2:2`
- `2`: equivalent to `4:2:0`

qtables If present, sets the qtables for the encoder. This is listed as an advanced option for wizards in the JPEG documentation. Use with caution. `qtables` can be one of several types of values:

- a string, naming a preset, e.g. `keep`, `web_low`, or `web_high`
- a list, tuple, or dictionary (with integer keys = `range(len(keys))`) of lists of 64 integers. There must be between 2 and 4 tables.

New in version 2.5.0.

Note: To enable JPEG support, you need to build and install the IJG JPEG library before building the Python Imaging Library. See the distribution README for details.

JPEG 2000

New in version 2.4.0.

Pillow reads and writes JPEG 2000 files containing L, LA, RGB or RGBA data. It can also read files containing YCbCr data, which it converts on read into RGB or RGBA depending on whether or not there is an alpha channel. Pillow

supports JPEG 2000 raw codestreams (.j2k files), as well as boxed JPEG 2000 files (.j2p or .jpx files). Pillow does *not* support files whose components have different sampling frequencies.

When loading, if you set the `mode` on the image prior to the `load()` method being invoked, you can ask Pillow to convert the image to either RGB or RGBA rather than choosing for itself. It is also possible to set `reduce` to the number of resolutions to discard (each one reduces the size of the resulting image by a factor of 2), and `layers` to specify the number of quality layers to load.

The `save()` method supports the following options:

offset The image offset, as a tuple of integers, e.g. (16, 16)

tile_offset The tile offset, again as a 2-tuple of integers.

tile_size The tile size as a 2-tuple. If not specified, or if set to None, the image will be saved without tiling.

quality_mode Either "rates" or "dB" depending on the units you want to use to specify image quality.

quality_layers A sequence of numbers, each of which represents either an approximate size reduction (if quality mode is "rates") or a signal to noise ratio value in decibels. If not specified, defaults to a single layer of full quality.

num_resolutions The number of different image resolutions to be stored (which corresponds to the number of Discrete Wavelet Transform decompositions plus one).

codeblock_size The code-block size as a 2-tuple. Minimum size is 4 x 4, maximum is 1024 x 1024, with the additional restriction that no code-block may have more than 4096 coefficients (i.e. the product of the two numbers must be no greater than 4096).

precinct_size The precinct size as a 2-tuple. Must be a power of two along both axes, and must be greater than the code-block size.

irreversible If True, use the lossy Irreversible Color Transformation followed by DWT 9-7. Defaults to False, which means to use the Reversible Color Transformation with DWT 5-3.

progression Controls the progression order; must be one of "LRCP", "RLCP", "RPCL", "PCRL", "CPRL". The letters stand for Component, Position, Resolution and Layer respectively and control the order of encoding, the idea being that e.g. an image encoded using LRCP mode can have its quality layers decoded as they arrive at the decoder, while one encoded using RLCP mode will have increasing resolutions decoded as they arrive, and so on.

cinema_mode Set the encoder to produce output compliant with the digital cinema specifications. The options here are "no" (the default), "cinema2k-24" for 24fps 2K, "cinema2k-48" for 48fps 2K, and "cinema4k-24" for 24fps 4K. Note that for compliant 2K files, *at least one* of your image dimensions must match 2048 x 1080, while for compliant 4K files, *at least one* of the dimensions must match 4096 x 2160.

Note: To enable JPEG 2000 support, you need to build and install the OpenJPEG library, version 2.0.0 or higher, before building the Python Imaging Library.

Windows users can install the OpenJPEG binaries available on the OpenJPEG website, but must add them to their PATH in order to use Pillow (if you fail to do this, you will get errors about not being able to load the `_imaging` DLL).

MSP

Pillow identifies and reads MSP files from Windows 1 and 2. The library writes uncompressed (Windows 1) versions of this format.

PCX

Pillow reads and writes PCX files containing 1, L, P, or RGB data.

PNG

Pillow identifies, reads, and writes PNG files containing 1, L, LA, I, P, RGB or RGBA data. Interlaced files are supported as of v1.1.7.

As of Pillow 6.0, EXIF data can be read from PNG images. However, unlike other image formats, EXIF data is not guaranteed to be present in `info` until `load()` has been called.

The `open()` method sets the following `info` properties, when appropriate:

chromaticity The chromaticity points, as an 8 tuple of floats. (White Point X, White Point Y, Red X, Red Y, Green X, Green Y, Blue X, Blue Y)

gamma Gamma, given as a floating point number.

srgb The sRGB rendering intent as an integer.

- 0 Perceptual
- 1 Relative Colorimetric
- 2 Saturation
- 3 Absolute Colorimetric

transparency For P images: Either the palette index for full transparent pixels, or a byte string with alpha values for each palette entry.

For 1, L, I and RGB images, the color that represents full transparent pixels in this image.

This key is omitted if the image is not a transparent palette image.

`open` also sets `Image.text` to a dictionary of the values of the `tEXt`, `zTXt`, and `iTXt` chunks of the PNG image. Individual compressed chunks are limited to a decompressed size of `PngImagePlugin.MAX_TEXT_CHUNK`, by default 1MB, to prevent decompression bombs. Additionally, the total size of all of the text chunks is limited to `PngImagePlugin.MAX_TEXT_MEMORY`, defaulting to 64MB.

The `save()` method supports the following options:

optimize If present and true, instructs the PNG writer to make the output file as small as possible. This includes extra processing in order to find optimal encoder settings.

transparency For P, 1, L, I, and RGB images, this option controls what color from the image to mark as transparent.

For P images, this can be either the palette index, or a byte string with alpha values for each palette entry.

dpi A tuple of two numbers corresponding to the desired dpi in each direction.

pnginfo A `PIL.PngImagePlugin.PngInfo` instance containing text tags.

compress_level ZLIB compression level, a number between 0 and 9: 1 gives best speed, 9 gives best compression, 0 gives no compression at all. Default is 6. When `optimize` option is True `compress_level` has no effect (it is set to 9 regardless of a value passed).

icc_profile The ICC Profile to include in the saved file.

exif The exif data to include in the saved file.

New in version 6.0.0.

bits (experimental) For P images, this option controls how many bits to store. If omitted, the PNG writer uses 8 bits (256 colors).

dictionary (experimental) Set the ZLIB encoder dictionary.

Note: To enable PNG support, you need to build and install the ZLIB compression library before building the Python Imaging Library. See the [installation documentation](#) for details.

APNG sequences

The PNG loader includes limited support for reading and writing Animated Portable Network Graphics (APNG) files. When an APNG file is loaded, `get_format_mimetype()` will return `"image/apng"`. The value of the `is_animated` property will be `True` when the `n_frames` property is greater than 1. For APNG files, the `n_frames` property depends on both the animation frame count as well as the presence or absence of a default image. See the `default_image` property documentation below for more details. The `seek()` and `tell()` methods are supported.

`im.seek()` raises an `EOFError` if you try to seek after the last frame.

These `info` properties will be set for APNG frames, where applicable:

default_image Specifies whether or not this APNG file contains a separate default image, which is not a part of the actual APNG animation.

When an APNG file contains a default image, the initially loaded image (i.e. the result of `seek(0)`) will be the default image. To account for the presence of the default image, the `n_frames` property will be set to `frame_count + 1`, where `frame_count` is the actual APNG animation frame count. To load the first APNG animation frame, `seek(1)` must be called.

- `True` - The APNG contains default image, which is not an animation frame.
- `False` - The APNG does not contain a default image. The `n_frames` property will be set to the actual APNG animation frame count. The initially loaded image (i.e. `seek(0)`) will be the first APNG animation frame.

loop The number of times to loop this APNG, 0 indicates infinite looping.

duration The time to display this APNG frame (in milliseconds).

Note: The APNG loader returns images the same size as the APNG file's logical screen size. The returned image contains the pixel data for a given frame, after applying any APNG frame disposal and frame blend operations (i.e. it contains what a web browser would render for this frame - the composite of all previous frames and this frame).

Any APNG file containing sequence errors is treated as an invalid image. The APNG loader will not attempt to repair and reorder files containing sequence errors.

Saving

When calling `save()`, by default only a single frame PNG file will be saved. To save an APNG file (including a single frame APNG), the `save_all` parameter must be set to `True`. The following parameters can also be set:

default_image Boolean value, specifying whether or not the base image is a default image. If `True`, the base image will be used as the default image, and the first image from the `append_images` sequence will be the first

APNG animation frame. If `False`, the base image will be used as the first APNG animation frame. Defaults to `False`.

append_images A list or tuple of images to append as additional frames. Each of the images in the list can be single or multiframe images. The size of each frame should match the size of the base image. Also note that if a frame's mode does not match that of the base image, the frame will be converted to the base image mode.

loop Integer number of times to loop this APNG, 0 indicates infinite looping. Defaults to 0.

duration Integer (or list or tuple of integers) length of time to display this APNG frame (in milliseconds). Defaults to 0.

disposal An integer (or list or tuple of integers) specifying the APNG disposal operation to be used for this frame before rendering the next frame. Defaults to 0.

- 0 (`APNG_DISPOSE_OP_NONE`, default) - No disposal is done on this frame before rendering the next frame.
- 1 (`PIL.PngImagePlugin.APNG_DISPOSE_OP_BACKGROUND`) - This frame's modified region is cleared to fully transparent black before rendering the next frame.
- 2 (`APNG_DISPOSE_OP_PREVIOUS`) - This frame's modified region is reverted to the previous frame's contents before rendering the next frame.

blend An integer (or list or tuple of integers) specifying the APNG blend operation to be used for this frame before rendering the next frame. Defaults to 0.

- 0 (`APNG_BLEND_OP_SOURCE`) - All color components of this frame, including alpha, overwrite the previous output image contents.
- 1 (`APNG_BLEND_OP_OVER`) - This frame should be alpha composited with the previous output image contents.

Note: The `duration`, `disposal` and `blend` parameters can be set to lists or tuples to specify values for each individual frame in the animation. The length of the list or tuple must be identical to the total number of actual frames in the APNG animation. If the APNG contains a default image (i.e. `default_image` is set to `True`), these list or tuple parameters should not include an entry for the default image.

PPM

Pillow reads and writes PBM, PGM, PPM and PNM files containing 1, L or RGB data.

SGI

Pillow reads and writes uncompressed L, RGB, and RGBA files.

SPIDER

Pillow reads and writes SPIDER image files of 32-bit floating point data ("F;32F").

Pillow also reads SPIDER stack files containing sequences of SPIDER images. The `seek()` and `tell()` methods are supported, and random access is allowed.

The `open()` method sets the following attributes:

format Set to `SPIDER`

istack Set to 1 if the file is an image stack, else 0.

n_frames Set to the number of images in the stack.

A convenience method, `convert2byte()`, is provided for converting floating point data to byte data (mode L):

```
im = Image.open('image001.spi').convert2byte()
```

Writing files in SPIDER format

The extension of SPIDER files may be any 3 alphanumeric characters. Therefore the output format must be specified explicitly:

```
im.save('newimage.spi', format='SPIDER')
```

For more information about the SPIDER image processing package, see the [SPIDER homepage at Wadsworth Center](#).

TGA

Pillow reads and writes TGA images containing L, LA, P, RGB, and RGBA data. Pillow can read and write both uncompressed and run-length encoded TGAs.

TIFF

Pillow reads and writes TIFF files. It can read both striped and tiled images, pixel and plane interleaved multi-band images. If you have `libtiff` and its headers installed, Pillow can read and write many kinds of compressed TIFF files. If not, Pillow will only read and write uncompressed files.

Note: Beginning in version 5.0.0, Pillow requires `libtiff` to read or write compressed files. Prior to that release, Pillow had buggy support for reading Packbits, LZW and JPEG compressed TIFFs without using `libtiff`.

The `open()` method sets the following `info` properties:

compression Compression mode.

New in version 2.0.0.

dpi Image resolution as an `(xdpi, ydpi)` tuple, where applicable. You can use the `tag` attribute to get more detailed information about the image resolution.

New in version 1.1.5.

resolution Image resolution as an `(xres, yres)` tuple, where applicable. This is a measurement in whichever unit is specified by the file.

New in version 1.1.5.

The `tag_v2` attribute contains a dictionary of TIFF metadata. The keys are numerical indexes from `TAGS_V2`. Values are strings or numbers for single items, multiple values are returned in a tuple of values. Rational numbers are returned as a *IFDRational* object.

New in version 3.0.0.

For compatibility with legacy code, the `tag` attribute contains a dictionary of decoded TIFF fields as returned prior to version 3.0.0. Values are returned as either strings or tuples of numeric values. Rational numbers are returned as a tuple of `(numerator, denominator)`.

Deprecated since version 3.0.0.

Reading Multi-frame TIFF Images

The TIFF loader supports the `seek()` and `tell()` methods, taking and returning frame numbers within the image file. You can combine these methods to seek to the next frame (`im.seek(im.tell() + 1)`). Frames are numbered from 0 to `im.num_frames - 1`, and can be accessed in any order.

`im.seek()` raises an `EOFError` if you try to seek after the last frame.

Saving Tiff Images

The `save()` method can take the following keyword arguments:

save_all If true, Pillow will save all frames of the image to a multiframe tiff document.

New in version 3.4.0.

append_images A list of images to append as additional frames. Each of the images in the list can be single or multiframe images. Note however, that for correct results, all the appended images should have the same `encoderinfo` and `encoderconfig` properties.

New in version 4.2.0.

tiffinfo A `ImageFileDirectory_v2` object or dict object containing tiff tags and values. The TIFF field type is autodetected for Numeric and string values, any other types require using an `ImageFileDirectory_v2` object and setting the type in `tagtype` with the appropriate numerical value from `TiffTags.TYPES`.

New in version 2.3.0.

Metadata values that are of the rational type should be passed in using a `IFDRational` object.

New in version 3.1.0.

For compatibility with legacy code, a `ImageFileDirectory_v1` object may be passed in this field. However, this is deprecated.

New in version 5.4.0.

Previous versions only supported some tags when writing using libtiff. The supported list is found in `LIBTIFF_CORE`.

New in version 6.1.0.

Added support for signed types (e.g. `TIFF_SIGNED_LONG`) and multiple values. Multiple values for a single tag must be to `ImageFileDirectory_v2` as a tuple and require a matching type in `tagtype`.

compression A string containing the desired compression method for the file. (valid only with libtiff installed) Valid compression methods are: `None`, `"tiff_ccitt"`, `"group3"`, `"group4"`, `"tiff_jpeg"`, `"tiff_adobe_deflate"`, `"tiff_thunderscan"`, `"tiff_deflate"`, `"tiff_sgilog"`, `"tiff_sgilog24"`, `"tiff_raw_16"`

quality The image quality for JPEG compression, on a scale from 0 (worst) to 100 (best). The default is 75.

New in version 6.1.0.

These arguments to set the tiff header fields are an alternative to using the general tags available through `tiffinfo`.

description

software

date_time

artist

copyright Strings

resolution_unit An integer. 1 for no unit, 2 for inches and 3 for centimeters.

resolution Either an integer or a float, used for both the x and y resolution.

x_resolution Either an integer or a float.

y_resolution Either an integer or a float.

dpi A tuple of (x_resolution, y_resolution), with inches as the resolution unit. For consistency with other image formats, the x and y resolutions of the dpi will be rounded to the nearest integer.

WebP

Pillow reads and writes WebP files. The specifics of Pillow's capabilities with this format are currently undocumented.

The `save()` method supports the following options:

lossless If present and true, instructs the WebP writer to use lossless compression.

quality Integer, 1-100, Defaults to 80. For lossy, 0 gives the smallest size and 100 the largest. For lossless, this parameter is the amount of effort put into the compression: 0 is the fastest, but gives larger files compared to the slowest, but best, 100.

method Quality/speed trade-off (0=fast, 6=slower-better). Defaults to 0.

icc_profile The ICC Profile to include in the saved file. Only supported if the system WebP library was built with webpmux support.

exif The exif data to include in the saved file. Only supported if the system WebP library was built with webpmux support.

Saving sequences

Note: Support for animated WebP files will only be enabled if the system WebP library is v0.5.0 or later. You can check webp animation support at runtime by calling `features.check("webp_anim")`.

When calling `save()` to write a WebP file, the following options are available when the `save_all` argument is present and true.

append_images A list of images to append as additional frames. Each of the images in the list can be single or multiframe images.

duration The display duration of each frame, in milliseconds. Pass a single integer for a constant duration, or a list or tuple to set the duration for each frame separately.

loop Number of times to repeat the animation. Defaults to [0 = infinite].

background Background color of the canvas, as an RGBA tuple with values in the range of (0-255).

minimize_size If true, minimize the output size (slow). Implicitly disables key-frame insertion.

kmin, kmax Minimum and maximum distance between consecutive key frames in the output. The library may insert some key frames as needed to satisfy this criteria. Note that these conditions should hold: `kmax > kmin` and

$kmin \geq kmax / 2 + 1$. Also, if $kmax \leq 0$, then key-frame insertion is disabled; and if $kmax == 1$, then all frames will be key-frames ($kmin$ value does not matter for these special cases).

allow_mixed If true, use mixed compression mode; the encoder heuristically chooses between lossy and lossless for each frame.

XBM

Pillow reads and writes X bitmap files (mode 1).

Read-only formats

BLP

BLP is the Blizzard Mipmap Format, a texture format used in World of Warcraft. Pillow supports reading JPEG Compressed or raw BLP1 images, and all types of BLP2 images.

CUR

CUR is used to store cursors on Windows. The CUR decoder reads the largest available cursor. Animated cursors are not supported.

DCX

DCX is a container file format for PCX files, defined by Intel. The DCX format is commonly used in fax applications. The DCX decoder can read files containing 1, L, P, or RGB data.

When the file is opened, only the first image is read. You can use *seek ()* or *ImageSequence* to read other images.

DDS

DDS is a popular container texture format used in video games and natively supported by DirectX. Currently, uncompressed RGB data and DXT1, DXT3, and DXT5 pixel formats are supported, and only in RGBA mode.

New in version 3.4.0: DXT3

FLI, FLC

Pillow reads Autodesk FLI and FLC animations.

The *open ()* method sets the following *info* properties:

duration The delay (in milliseconds) between each frame.

FPX

Pillow reads Kodak FlashPix files. In the current version, only the highest resolution image is read from the file, and the viewing transform is not taken into account.

Note: To enable full FlashPix support, you need to build and install the IJG JPEG library before building the Python Imaging Library. See the distribution README for details.

FTEX

New in version 3.2.0.

The FTEX decoder reads textures used for 3D objects in Independence War 2: Edge Of Chaos. The plugin reads a single texture per file, in the compressed and uncompressed formats.

GBR

The GBR decoder reads GIMP brush files, version 1 and 2.

The `open()` method sets the following `info` properties:

comment The brush name.

spacing The spacing between the brushes, in pixels. Version 2 only.

GD

Pillow reads uncompressed GD2 files. Note that you must use `PIL.GdImageFile.open()` to read such a file.

The `open()` method sets the following `info` properties:

transparency Transparency color index. This key is omitted if the image is not transparent.

IMT

Pillow reads Image Tools images containing L data.

IPTC/NAA

Pillow provides limited read support for IPTC/NAA newsphoto files.

MCIDAS

Pillow identifies and reads 8-bit McIDAS area files.

MIC

Pillow identifies and reads Microsoft Image Composer (MIC) files. When opened, the first sprite in the file is loaded. You can use `seek()` and `tell()` to read other sprites from the file.

Note that there may be an embedded gamma of 2.2 in MIC files.

MPO

Pillow identifies and reads Multi Picture Object (MPO) files, loading the primary image when first opened. The `seek()` and `tell()` methods may be used to read other pictures from the file. The pictures are zero-indexed and random access is supported.

PCD

Pillow reads PhotoCD files containing RGB data. This only reads the 768x512 resolution image from the file. Higher resolutions are encoded in a proprietary encoding.

PIXAR

Pillow provides limited support for PIXAR raster files. The library can identify and read “dumped” RGB files. The format code is `PIXAR`.

PSD

Pillow identifies and reads PSD files written by Adobe Photoshop 2.5 and 3.0.

WAL

New in version 1.1.4.

Pillow reads Quake2 WAL texture files.

Note that this file format cannot be automatically identified, so you must use the `open` function in the `WalImageFile` module to read files in this format.

By default, a Quake2 standard palette is attached to the texture. To override the palette, use the `putpalette` method.

WMF

Pillow can identify WMF files.

On Windows, it can read WMF files. By default, it will load the image at 72 dpi. To load it at another resolution:

```
from PIL import Image
with Image.open("drawing.wmf") as im:
    im.load(dpi=144)
```

To add other read or write support, use `PIL.WmfImagePlugin.register_handler()` to register a WMF handler.

```
from PIL import Image
from PIL import WmfImagePlugin

class WmfHandler:
    def open(self, im):
        ...
    def load(self, im):
```

(continues on next page)

(continued from previous page)

```

    ...
    return image
    def save(self, im, fp, filename):
        ...

wmf_handler = WmfHandler()
WmfImagePlugin.register_handler(wmf_handler)

im = Image.open("sample.wmf")

```

XPM

Pillow reads X pixmap files (mode P) with 256 colors or less.

The `open()` method sets the following `info` properties:

transparency Transparency color index. This key is omitted if the image is not transparent.

Write-only formats

PALM

Pillow provides write-only support for PALM pixmap files.

The format code is `Palm`, the extension is `.palm`.

PDF

Pillow can write PDF (Acrobat) images. Such images are written as binary PDF 1.4 files, using either JPEG or HEX encoding depending on the image mode (and whether JPEG support is available or not).

The `save()` method can take the following keyword arguments:

save_all If a multiframe image is used, by default, only the first image will be saved. To save all frames, each frame to a separate page of the PDF, the `save_all` parameter must be present and set to `True`.

New in version 3.0.0.

append_images A list of images to append as additional pages. Each of the images in the list can be single or multiframe images.

New in version 4.2.0.

append Set to `True` to append pages to an existing PDF file. If the file doesn't exist, an `IOError` will be raised.

New in version 5.1.0.

resolution Image resolution in DPI. This, together with the number of pixels in the image, will determine the physical dimensions of the page that will be saved in the PDF.

title The document's title. If not appending to an existing PDF file, this will default to the filename.

New in version 5.1.0.

author The name of the person who created the document.

New in version 5.1.0.

subject The subject of the document.

New in version 5.1.0.

keywords Keywords associated with the document.

New in version 5.1.0.

creator If the document was converted to PDF from another format, the name of the conforming product that created the original document from which it was converted.

New in version 5.1.0.

producer If the document was converted to PDF from another format, the name of the conforming product that converted it to PDF.

New in version 5.1.0.

creationDate The creation date of the document. If not appending to an existing PDF file, this will default to the current time.

New in version 5.3.0.

modDate The modification date of the document. If not appending to an existing PDF file, this will default to the current time.

New in version 5.3.0.

XV Thumbnails

Pillow can read XV thumbnail files.

Identify-only formats

BUFR

New in version 1.1.3.

Pillow provides a stub driver for BUFR files.

To add read or write support to your application, use `PIL.BufrStubImagePlugin.register_handler()`.

FITS

New in version 1.1.5.

Pillow provides a stub driver for FITS files.

To add read or write support to your application, use `PIL.FitsStubImagePlugin.register_handler()`.

GRIB

New in version 1.1.5.

Pillow provides a stub driver for GRIB files.

The driver requires the file to start with a GRIB header. If you have files with embedded GRIB data, or files with multiple GRIB fields, your application has to seek to the header before passing the file handle to Pillow.

To add read or write support to your application, use `PIL.GribStubImagePlugin.register_handler()`.

HDF5

New in version 1.1.5.

Pillow provides a stub driver for HDF5 files.

To add read or write support to your application, use `PIL.Hdf5StubImagePlugin.register_handler()`.

MPEG

Pillow identifies MPEG files.

2.4.2 Writing Your Own Image Plugin

The Pillow uses a plug-in model which allows you to add your own decoders to the library, without any changes to the library itself. Such plug-ins usually have names like `XxxImagePlugin.py`, where `Xxx` is a unique format name (usually an abbreviation).

Warning: Pillow \geq 2.1.0 no longer automatically imports any file in the Python path with a name ending in `ImagePlugin.py`. You will need to import your image plugin manually.

Pillow decodes files in 2 stages:

1. It loops over the available image plugins in the loaded order, and calls the plugin's `accept` function with the first 16 bytes of the file. If the `accept` function returns true, the plugin's `_open` method is called to set up the image metadata and image tiles. The `_open` method is not for decoding the actual image data.
2. When the image data is requested, the `ImageFile.load` method is called, which sets up a decoder for each tile and feeds the data to it.

An image plug-in should contain a format handler derived from the `PIL.ImageFile.ImageFile` base class. This class should provide an `_open()` method, which reads the file header and sets up at least the `mode` and `size` attributes. To be able to load the file, the method must also create a list of `tile` descriptors, which contain a decoder name, extents of the tile, and any decoder-specific data. The format handler class must be explicitly registered, via a call to the `Image` module.

Note: For performance reasons, it is important that the `_open()` method quickly rejects files that do not have the appropriate contents.

Example

The following plug-in supports a simple format, which has a 128-byte header consisting of the words “SPAM” followed by the width, height, and pixel size in bits. The header fields are separated by spaces. The image data follows directly after the header, and can be either bi-level, greyscale, or 24-bit true color.

SpamImagePlugin.py:

```

from PIL import Image, ImageFile

class SpamImageFile(ImageFile.ImageFile):

    format = "SPAM"
    format_description = "Spam raster image"

    def _open(self):

        # check header
        header = self.fp.read(128)
        if header[:4] != b"SPAM":
            raise SyntaxError("not a SPAM file")

        header = header.split()

        # size in pixels (width, height)
        self._size = int(header[1]), int(header[2])

        # mode setting
        bits = int(header[3])
        if bits == 1:
            self.mode = "1"
        elif bits == 8:
            self.mode = "L"
        elif bits == 24:
            self.mode = "RGB"
        else:
            raise SyntaxError("unknown number of bits")

        # data descriptor
        self.tile = [
            ("raw", (0, 0) + self.size, 128, (self.mode, 0, 1))
        ]

Image.register_open(SpamImageFile.format, SpamImageFile)

Image.register_extension(SpamImageFile.format, ".spam")
Image.register_extension(SpamImageFile.format, ".spa") # dos version

```

The format handler must always set the `size` and `mode` attributes. If these are not set, the file cannot be opened. To simplify the plugin, the calling code considers exceptions like `SyntaxError`, `KeyError`, `IndexError`, `EOFError` and `struct.error` as a failure to identify the file.

Note that the image plugin must be explicitly registered using `PIL.Image.register_open()`. Although not required, it is also a good idea to register any extensions used by this format.

The `tile` attribute

To be able to read the file as well as just identifying it, the `tile` attribute must also be set. This attribute consists of a list of tile descriptors, where each descriptor specifies how data should be loaded to a given region in the image. In most cases, only a single descriptor is used, covering the full image.

The tile descriptor is a 4-tuple with the following contents:

```
(decoder, region, offset, parameters)
```


The fields are used as follows:

decoder Specifies which decoder to use. The `raw` decoder used here supports uncompressed data, in a variety of pixel formats. For more information on this decoder, see the description below.

region A 4-tuple specifying where to store data in the image.

offset Byte offset from the beginning of the file to image data.

parameters Parameters to the decoder. The contents of this field depends on the decoder specified by the first field in the tile descriptor tuple. If the decoder doesn't need any parameters, use `None` for this field.

Note that the `tile` attribute contains a list of tile descriptors, not just a single descriptor.

2.4.3 Decoders

The raw decoder

The `raw` decoder is used to read uncompressed data from an image file. It can be used with most uncompressed file formats, such as PPM, BMP, uncompressed TIFF, and many others. To use the raw decoder with the `PIL.Image.frombytes()` function, use the following syntax:

```
image = Image.frombytes(
    mode, size, data, "raw",
    raw mode, stride, orientation
)
```

When used in a tile descriptor, the parameter field should look like:

```
(raw mode, stride, orientation)
```

The fields are used as follows:

raw mode The pixel layout used in the file, and is used to properly convert data to PIL's internal layout. For a summary of the available formats, see the table below.

stride The distance in bytes between two consecutive lines in the image. If 0, the image is assumed to be packed (no padding between lines). If omitted, the stride defaults to 0.

orientation Whether the first line in the image is the top line on the screen (1), or the bottom line (-1). If omitted, the orientation defaults to 1.

The **raw mode** field is used to determine how the data should be unpacked to match PIL's internal pixel layout. PIL supports a large set of raw modes; for a complete list, see the table in the `Unpack.c` module. The following table describes some commonly used **raw modes**:

mode	description
1	1-bit bilevel, stored with the leftmost pixel in the most significant bit. 0 means black, 1 means white.
1; I	1-bit inverted bilevel, stored with the leftmost pixel in the most significant bit. 0 means white, 1 means black.
1; R	1-bit reversed bilevel, stored with the leftmost pixel in the least significant bit. 0 means black, 1 means white.
L	8-bit greyscale. 0 means black, 255 means white.
L; I	8-bit inverted greyscale. 0 means white, 255 means black.
P	8-bit palette-mapped image.
RGB	24-bit true colour, stored as (red, green, blue).
BGR	24-bit true colour, stored as (blue, green, red).
RGBX	24-bit true colour, stored as (red, green, blue, pad). The pad pixels may vary.
RGB; L	24-bit true colour, line interleaved (first all red pixels, then all green pixels, finally all blue pixels).

Note that for the most common cases, the raw mode is simply the same as the mode.

The Python Imaging Library supports many other decoders, including JPEG, PNG, and PackBits. For details, see the `decode.c` source file, and the standard plug-in implementations provided with the library.

Decoding floating point data

PIL provides some special mechanisms to allow you to load a wide variety of formats into a mode `F` (floating point) image memory.

You can use the `raw` decoder to read images where data is packed in any standard machine data type, using one of the following raw modes:

mode	description
F	32-bit native floating point.
F; 8	8-bit unsigned integer.
F; 8S	8-bit signed integer.
F; 16	16-bit little endian unsigned integer.
F; 16S	16-bit little endian signed integer.
F; 16B	16-bit big endian unsigned integer.
F; 16BS	16-bit big endian signed integer.
F; 16N	16-bit native unsigned integer.
F; 16NS	16-bit native signed integer.
F; 32	32-bit little endian unsigned integer.
F; 32S	32-bit little endian signed integer.
F; 32B	32-bit big endian unsigned integer.
F; 32BS	32-bit big endian signed integer.
F; 32N	32-bit native unsigned integer.
F; 32NS	32-bit native signed integer.
F; 32F	32-bit little endian floating point.
F; 32BF	32-bit big endian floating point.
F; 32NF	32-bit native floating point.
F; 64F	64-bit little endian floating point.
F; 64BF	64-bit big endian floating point.
F; 64NF	64-bit native floating point.

The bit decoder

If the raw decoder cannot handle your format, PIL also provides a special “bit” decoder that can be used to read various packed formats into a floating point image memory.

To use the bit decoder with the `PIL.Image.frombytes()` function, use the following syntax:

```
image = Image.frombytes(
    mode, size, data, "bit",
    bits, pad, fill, sign, orientation
)
```

When used in a tile descriptor, the parameter field should look like:

```
(bits, pad, fill, sign, orientation)
```

The fields are used as follows:

bits Number of bits per pixel (2-32). No default.

pad Padding between lines, in bits. This is either 0 if there is no padding, or 8 if lines are padded to full bytes. If omitted, the pad value defaults to 8.

fill Controls how data are added to, and stored from, the decoder bit buffer.

fill=0 Add bytes to the LSB end of the decoder buffer; store pixels from the MSB end.

fill=1 Add bytes to the MSB end of the decoder buffer; store pixels from the MSB end.

fill=2 Add bytes to the LSB end of the decoder buffer; store pixels from the LSB end.

fill=3 Add bytes to the MSB end of the decoder buffer; store pixels from the LSB end.

If omitted, the fill order defaults to 0.

sign If non-zero, bit fields are sign extended. If zero or omitted, bit fields are unsigned.

orientation Whether the first line in the image is the top line on the screen (1), or the bottom line (-1). If omitted, the orientation defaults to 1.

2.4.4 Writing Your Own File Decoder in C

There are 3 stages in a file decoder’s lifetime:

1. Setup: Pillow looks for a function in the decoder registry, falling back to a function named `[decodername]_decoder` on the internal core image object. That function is called with the `args` tuple from the tile setup in the `_open` method.
2. Decoding: The decoder’s `decode` function is repeatedly called with chunks of image data.
3. Cleanup: If the decoder has registered a cleanup function, it will be called at the end of the decoding process, even if there was an exception raised.

Setup

The current conventions are that the decoder setup function is named `PyImaging_[Decodername]DecoderNew` and defined in `decode.c`. The python binding for it is named `[decodername]_decoder` and is setup from within the `_imaging.c` file in the codecs section of the function array.

The setup function needs to call `PyImaging_DecoderNew` and at the very least, set the `decode` function pointer. The fields of interest in this object are:

decode Function pointer to the decode function, which has access to `im`, `state`, and the buffer of data to be added to the image.

cleanup Function pointer to the cleanup function, has access to `state`.

im The target image, will be set by Pillow.

state An `ImagingCodecStateInstance`, will be set by Pillow. The **context** member is an opaque struct that can be used by the decoder to store any format specific state or options.

pulls_fd **EXPERIMENTAL – WARNING**, interface may change. If set to 1, `state->fd` will be a pointer to the Python file like object. The decoder may use the functions in `codec_fd.c` to read directly from the file like object rather than have the data pushed through a buffer. Note that this implementation may be refactored until this warning is removed.

New in version 3.3.0.

Decoding

The decode function is called with the target (core) image, the decoder state structure, and a buffer of data to be decoded.

Experimental – If `pulls_fd` is set, then the decode function is called once, with an empty buffer. It is the decoder's responsibility to decode the entire tile in that one call. The rest of this section only applies if `pulls_fd` is not set.

It is the decoder's responsibility to pull as much data as possible out of the buffer and return the number of bytes consumed. The next call to the decoder will include the previous unconsumed tail. The decoder function will be called multiple times as the data is read from the file like object.

If an error occurs, set `state->errcode` and return -1.

Return -1 on success, without setting the `errcode`.

Cleanup

The cleanup function is called after the decoder returns a negative value, or if there is a read error from the file. This function should free any allocated memory and release any resources from external libraries.

2.4.5 Writing Your Own File Decoder in Python

Python file decoders should derive from `PIL.ImageFile.PyDecoder` and should at least override the `decode` method. File decoders should be registered using `PIL.Image.register_decoder()`. As in the C implementation of the file decoders, there are three stages in the lifetime of a Python-based file decoder:

1. Setup: Pillow looks for the decoder in the registry, then instantiates the class.
2. Decoding: The decoder instance's `decode` method is repeatedly called with a buffer of data to be interpreted.
3. Cleanup: The decoder instance's `cleanup` method is called.

3.1 Image Module

The *Image* module provides a class with the same name which is used to represent a PIL image. The module also provides a number of factory functions, including functions to load images from files, and to create new images.

3.1.1 Examples

Open, rotate, and display an image (using the default viewer)

The following script loads an image, rotates it 45 degrees, and displays it using an external viewer (usually xv on Unix, and the Paint program on Windows).

```
from PIL import Image
im = Image.open("bride.jpg")
im.rotate(45).show()
```

Create thumbnails

The following script creates nice thumbnails of all JPEG images in the current directory preserving aspect ratios with 128x128 max resolution.

```
from PIL import Image
import glob, os

size = 128, 128

for infile in glob.glob("*.jpg"):
    file, ext = os.path.splitext(infile)
    im = Image.open(infile)
```

(continues on next page)

(continued from previous page)

```
im.thumbnail(size)
im.save(file + ".thumbnail", "JPEG")
```

3.1.2 Functions

`PIL.Image.open(fp, mode='r')`

Opens and identifies the given image file.

This is a lazy operation; this function identifies the file, but the file remains open and the actual image data is not read from the file until you try to process the data (or call the `load()` method). See `new()`. See *File Handling in Pillow*.

Parameters

- **fp** – A filename (string), `pathlib.Path` object or a file object. The file object must implement `read()`, `seek()`, and `tell()` methods, and be opened in binary mode.
- **mode** – The mode. If given, this argument must be “r”.

Returns An *Image* object.

Raises

- **FileNotFoundError** – If the file cannot be found.
- **PIL.UnidentifiedImageError** – If the image cannot be opened and identified.
- **ValueError** – If the mode is not “r”, or if a `StringIO` instance is used for `fp`.

Warning: To protect against potential DOS attacks caused by “decompression bombs” (i.e. malicious files which decompress into a huge amount of data and are designed to crash or cause disruption by using up a lot of memory), Pillow will issue a `DecompressionBombWarning` if the image is over a certain limit. If desired, the warning can be turned into an error with `warnings.simplefilter('error', Image.DecompressionBombWarning)` or suppressed entirely with `warnings.simplefilter('ignore', Image.DecompressionBombWarning)`. See also [the logging documentation](#) to have warnings output to the logging facility instead of `stderr`.

Image processing

`PIL.Image.alpha_composite(im1, im2)`

Alpha composite `im2` over `im1`.

Parameters

- **im1** – The first image. Must have mode `RGBA`.
- **im2** – The second image. Must have mode `RGBA`, and the same size as the first image.

Returns An *Image* object.

`PIL.Image.blend(im1, im2, alpha)`

Creates a new image by interpolating between two input images, using a constant `alpha`:

```
out = image1 * (1.0 - alpha) + image2 * alpha
```

Parameters

- **im1** – The first image.
- **im2** – The second image. Must have the same mode and size as the first image.
- **alpha** – The interpolation alpha factor. If alpha is 0.0, a copy of the first image is returned. If alpha is 1.0, a copy of the second image is returned. There are no restrictions on the alpha value. If necessary, the result is clipped to fit into the allowed output range.

Returns An *Image* object.

`PIL.Image.composite` (*image1*, *image2*, *mask*)

Create composite image by blending images using a transparency mask.

Parameters

- **image1** – The first image.
- **image2** – The second image. Must have the same mode and size as the first image.
- **mask** – A mask image. This image can have mode “1”, “L”, or “RGBA”, and must have the same size as the other two images.

`PIL.Image.eval` (*image*, **args*)

Applies the function (which should take one argument) to each pixel in the given image. If the image has more than one band, the same function is applied to each band. Note that the function is evaluated once for each possible pixel value, so you cannot use random components or other generators.

Parameters

- **image** – The input image.
- **function** – A function object, taking one integer argument.

Returns An *Image* object.

`PIL.Image.merge` (*mode*, *bands*)

Merge a set of single band images into a new multiband image.

Parameters

- **mode** – The mode to use for the output image. See: *Modes*.
- **bands** – A sequence containing one single-band image for each band in the output image. All bands must have the same size.

Returns An *Image* object.

Constructing images

`PIL.Image.new` (*mode*, *size*, *color=0*)

Creates a new image with the given mode and size.

Parameters

- **mode** – The mode to use for the new image. See: *Modes*.
- **size** – A 2-tuple, containing (width, height) in pixels.
- **color** – What color to use for the image. Default is black. If given, this should be a single integer or floating point value for single-band modes, and a tuple for multi-band modes (one value per band). When creating RGB images, you can also use color strings as supported by the ImageColor module. If the color is None, the image is not initialised.

Returns An *Image* object.

PIL. `Image.fromarray` (*obj*, *mode=None*)

Creates an image memory from an object exporting the array interface (using the buffer protocol).

If **obj** is not contiguous, then the `tobytes` method is called and `frombuffer()` is used.

If you have an image in NumPy:

```
from PIL import Image
import numpy as np
im = Image.open('hopper.jpg')
a = np.asarray(im)
```

Then this can be used to convert it to a Pillow image:

```
im = Image.fromarray(a)
```

Parameters

- **obj** – Object with array interface
- **mode** – Mode to use (will be determined from type if None) See: *Modes*.

Returns An image object.

New in version 1.1.6.

PIL. `Image.frombytes` (*mode*, *size*, *data*, *decoder_name='raw'*, **args*)

Creates a copy of an image memory from pixel data in a buffer.

In its simplest form, this function takes three arguments (mode, size, and unpacked pixel data).

You can also use any pixel decoder supported by PIL. For more information on available decoders, see the section *Writing Your Own File Decoder*.

Note that this function decodes pixel data only, not entire images. If you have an entire image in a string, wrap it in a `BytesIO` object, and use `open()` to load it.

Parameters

- **mode** – The image mode. See: *Modes*.
- **size** – The image size.
- **data** – A byte buffer containing raw data for the given mode.
- **decoder_name** – What decoder to use.
- **args** – Additional parameters for the given decoder.

Returns An *Image* object.

PIL. `Image.fromstring` (**args*, ***kw*)

PIL. `Image.frombuffer` (*mode*, *size*, *data*, *decoder_name='raw'*, **args*)

Creates an image memory referencing pixel data in a byte buffer.

This function is similar to `frombytes()`, but uses data in the byte buffer, where possible. This means that changes to the original buffer object are reflected in this image). Not all modes can share memory; supported modes include “L”, “RGBX”, “RGBA”, and “CMYK”.

Note that this function decodes pixel data only, not entire images. If you have an entire image file in a string, wrap it in a `BytesIO` object, and use `open()` to load it.

In the current version, the default parameters used for the “raw” decoder differs from that used for `frombytes()`. This is a bug, and will probably be fixed in a future release. The current release issues a

warning if you do this; to disable the warning, you should provide the full set of parameters. See below for details.

Parameters

- **mode** – The image mode. See: *Modes*.
- **size** – The image size.
- **data** – A bytes or other buffer object containing raw data for the given mode.
- **decoder_name** – What decoder to use.
- **args** – Additional parameters for the given decoder. For the default encoder (“raw”), it’s recommended that you provide the full set of parameters:

```
frombuffer(mode, size, data, "raw", mode, 0, 1)
```

Returns An *Image* object.

New in version 1.1.4.

Registering plugins

Note: These functions are for use by plugin authors. Application authors can ignore them.

`PIL.Image.register_open` (*id*, *factory*, *accept=None*)

Register an image file plugin. This function should not be used in application code.

Parameters

- **id** – An image format identifier.
- **factory** – An image file factory method.
- **accept** – An optional function that can be used to quickly reject images having another format.

`PIL.Image.register_decoder` (*name*, *decoder*)

Registers an image decoder. This function should not be used in application code.

Parameters

- **name** – The name of the decoder
- **decoder** – A callable(mode, args) that returns an `ImageFile.PyDecoder` object

New in version 4.1.0.

`PIL.Image.register_mime` (*id*, *mimetype*)

Registers an image MIME type. This function should not be used in application code.

Parameters

- **id** – An image format identifier.
- **mimetype** – The image MIME type for this format.

`PIL.Image.register_save` (*id*, *driver*)

Registers an image save function. This function should not be used in application code.

Parameters

- **id** – An image format identifier.
- **driver** – A function to save images in this format.

`PIL.Image.register_encoder` (*name, encoder*)

Registers an image encoder. This function should not be used in application code.

Parameters

- **name** – The name of the encoder
- **encoder** – A callable(mode, args) that returns an `ImageFile.PyEncoder` object

New in version 4.1.0.

`PIL.Image.register_extension` (*id, extension*)

Registers an image extension. This function should not be used in application code.

Parameters

- **id** – An image format identifier.
- **extension** – An extension used for this format.

3.1.3 The Image Class

class `PIL.Image.Image`

This class represents an image object. To create *Image* objects, use the appropriate factory functions. There’s hardly ever any reason to call the `Image` constructor directly.

- `open()`
- `new()`
- `frombytes()`

An instance of the *Image* class has the following methods. Unless otherwise stated, all methods return a new instance of the *Image* class, holding the resulting image.

`Image.alpha_composite` (*im, dest=(0, 0), source=(0, 0)*)

‘In-place’ analog of `Image.alpha_composite`. Composites an image onto this image.

Parameters

- **im** – image to composite over this one
- **dest** – Optional 2 tuple (left, top) specifying the upper left corner in this (destination) image.
- **source** – Optional 2 (left, top) tuple for the upper left corner in the overlay source image, or 4 tuple (left, top, right, bottom) for the bounds of the source rectangle

Performance Note: Not currently implemented in-place in the core layer.

`Image.convert` (*mode=None, matrix=None, dither=None, palette=0, colors=256*)

Returns a converted copy of this image. For the “P” mode, this method translates pixels through the palette. If mode is omitted, a mode is chosen so that all information in the image and the palette can be represented without a palette.

The current version supports all possible conversions between “L”, “RGB” and “CMYK.” The **matrix** argument only supports “L” and “RGB”.

When translating a color image to greyscale (mode “L”), the library uses the ITU-R 601-2 luma transform:

```
L = R * 299/1000 + G * 587/1000 + B * 114/1000
```

The default method of converting a greyscale (“L”) or “RGB” image into a bilevel (mode “1”) image uses Floyd-Steinberg dither to approximate the original image luminosity levels. If dither is NONE, all values larger than 128 are set to 255 (white), all other values to 0 (black). To use other thresholds, use the `point()` method.

When converting from “RGBA” to “P” without a **matrix** argument, this passes the operation to `quantize()`, and **dither** and **palette** are ignored.

Parameters

- **mode** – The requested mode. See: *Modes*.
- **matrix** – An optional conversion matrix. If given, this should be 4- or 12-tuple containing floating point values.
- **dither** – Dithering method, used when converting from mode “RGB” to “P” or from “RGB” or “L” to “1”. Available methods are NONE or FLOYDSTEINBERG (default). Note that this is not used when **matrix** is supplied.
- **palette** – Palette to use when converting from mode “RGB” to “P”. Available palettes are WEB or ADAPTIVE.
- **colors** – Number of colors to use for the ADAPTIVE palette. Defaults to 256.

Return type *Image*

Returns An *Image* object.

The following example converts an RGB image (linearly calibrated according to ITU-R 709, using the D65 luminant) to the CIE XYZ color space:

```
rgb2xyz = (
    0.412453, 0.357580, 0.180423, 0,
    0.212671, 0.715160, 0.072169, 0,
    0.019334, 0.119193, 0.950227, 0)
out = im.convert("RGB", rgb2xyz)
```

`Image.copy()`

Copies this image. Use this method if you wish to paste things into an image, but still retain the original.

Return type *Image*

Returns An *Image* object.

`Image.crop(box=None)`

Returns a rectangular region from this image. The box is a 4-tuple defining the left, upper, right, and lower pixel coordinate. See *Coordinate System*.

Note: Prior to Pillow 3.4.0, this was a lazy operation.

Parameters **box** – The crop rectangle, as a (left, upper, right, lower)-tuple.

Return type *Image*

Returns An *Image* object.

This crops the input image with the provided coordinates:

```
from PIL import Image

im = Image.open("hopper.jpg")
```

(continues on next page)

(continued from previous page)

```
# The crop method from the Image module takes four coordinates as input.
# The right can also be represented as (left+width)
# and lower can be represented as (upper+height).
(left, upper, right, lower) = (20, 20, 100, 100)

# Here the image "im" is cropped and assigned to new variable im_crop
im_crop = im.crop((left, upper, right, lower))
```

`Image.draft` (*mode*, *size*)

Configures the image file loader so it returns a version of the image that as closely as possible matches the given mode and size. For example, you can use this method to convert a color JPEG to greyscale while loading it.

If any changes are made, returns a tuple with the chosen mode and `box` with coordinates of the original image within the altered one.

Note that this method modifies the *Image* object in place. If the image has already been loaded, this method has no effect.

Note: This method is not implemented for most images. It is currently implemented only for JPEG and MPO images.

Parameters

- **mode** – The requested mode.
- **size** – The requested size.

`Image.filter` (*filter*)

Filters this image using the given filter. For a list of available filters, see the *ImageFilter* module.

Parameters **filter** – Filter kernel.

Returns An *Image* object.

This blurs the input image using a filter from the *ImageFilter* module:

```
from PIL import Image, ImageFilter

im = Image.open("hopper.jpg")

# Blur the input image using the filter ImageFilter.BLUR
im_blurred = im.filter(filter=ImageFilter.BLUR)
```

`Image.getbands` ()

Returns a tuple containing the name of each band in this image. For example, **getbands** on an RGB image returns (“R”, “G”, “B”).

Returns A tuple containing band names.

Return type tuple

This helps to get the bands of the input image:

```
from PIL import Image

im = Image.open("hopper.jpg")
print(im.getbands()) # Returns ('R', 'G', 'B')
```

`Image.getbbox` ()

Calculates the bounding box of the non-zero regions in the image.

Returns The bounding box is returned as a 4-tuple defining the left, upper, right, and lower pixel coordinate. See *Coordinate System*. If the image is completely empty, this method returns None.

This helps to get the bounding box coordinates of the input image:

```
from PIL import Image

im = Image.open("hopper.jpg")
print(im.getbbox())
# Returns four coordinates in the format (left, upper, right, lower)
```

`Image.getcolors` (*maxcolors=256*)

Returns a list of colors used in this image.

Parameters **maxcolors** – Maximum number of colors. If this number is exceeded, this method returns None. The default limit is 256 colors.

Returns An unsorted list of (count, pixel) values.

`Image.getdata` (*band=None*)

Returns the contents of this image as a sequence object containing pixel values. The sequence object is flattened, so that values for line one follow directly after the values of line zero, and so on.

Note that the sequence object returned by this method is an internal PIL data type, which only supports certain sequence operations. To convert it to an ordinary sequence (e.g. for printing), use `list(im.getdata())`.

Parameters **band** – What band to return. The default is to return all bands. To return a single band, pass in the index value (e.g. 0 to get the “R” band from an “RGB” image).

Returns A sequence-like object.

`Image.getextrema` ()

Gets the the minimum and maximum pixel values for each band in the image.

Returns For a single-band image, a 2-tuple containing the minimum and maximum pixel value. For a multi-band image, a tuple containing one 2-tuple for each band.

`Image.getpalette` ()

Returns the image palette as a list.

Returns A list of color values [r, g, b, ...], or None if the image has no palette.

`Image.getpixel` (*xy*)

Returns the pixel value at a given position.

Parameters **xy** – The coordinate, given as (x, y). See *Coordinate System*.

Returns The pixel value. If the image is a multi-layer image, this method returns a tuple.

`Image.histogram` (*mask=None, extrema=None*)

Returns a histogram for the image. The histogram is returned as a list of pixel counts, one for each pixel value in the source image. If the image has more than one band, the histograms for all bands are concatenated (for example, the histogram for an “RGB” image contains 768 values).

A bilevel image (mode “1”) is treated as a greyscale (“L”) image by this method.

If a mask is provided, the method returns a histogram for those parts of the image where the mask image is non-zero. The mask image must have the same size as the image, and be either a bi-level image (mode “1”) or a greyscale image (“L”).

Parameters

- **mask** – An optional mask.
- **extrema** – An optional tuple of manually-specified extrema.

Returns A list containing pixel counts.

`Image.offset` (*xoffset*, *yoffset=None*)

`Image.paste` (*im*, *box=None*, *mask=None*)

Pastes another image into this image. The box argument is either a 2-tuple giving the upper left corner, a 4-tuple defining the left, upper, right, and lower pixel coordinate, or None (same as (0, 0)). See *Coordinate System*. If a 4-tuple is given, the size of the pasted image must match the size of the region.

If the modes don't match, the pasted image is converted to the mode of this image (see the `convert()` method for details).

Instead of an image, the source can be a integer or tuple containing pixel values. The method then fills the region with the given color. When creating RGB images, you can also use color strings as supported by the ImageColor module.

If a mask is given, this method updates only the regions indicated by the mask. You can use either "1", "L" or "RGBA" images (in the latter case, the alpha band is used as mask). Where the mask is 255, the given image is copied as is. Where the mask is 0, the current value is preserved. Intermediate values will mix the two images together, including their alpha channels if they have them.

See `alpha_composite()` if you want to combine images with respect to their alpha channels.

Parameters

- **im** – Source image or pixel value (integer or tuple).
- **box** – An optional 4-tuple giving the region to paste into. If a 2-tuple is used instead, it's treated as the upper left corner. If omitted or None, the source is pasted into the upper left corner.

If an image is given as the second argument and there is no third, the box defaults to (0, 0), and the second argument is interpreted as a mask image.
- **mask** – An optional mask image.

`Image.point` (*lut*, *mode=None*)

Maps this image through a lookup table or function.

Parameters

- **lut** – A lookup table, containing 256 (or 65536 if `self.mode=="I"` and `mode=="L"`) values per band in the image. A function can be used instead, it should take a single argument. The function is called once for each possible pixel value, and the resulting table is applied to all bands of the image.
- **mode** – Output mode (default is same as input). In the current version, this can only be used if the source image has mode "L" or "P", and the output has mode "1" or the source image mode is "I" and the output mode is "L".

Returns An *Image* object.

`Image.putalpha` (*alpha*)

Adds or replaces the alpha layer in this image. If the image does not have an alpha layer, it's converted to "LA" or "RGBA". The new layer must be either "L" or "1".

Parameters **alpha** – The new alpha layer. This can either be an "L" or "1" image having the same size as this image, or an integer or other color value.

`Image.putdata` (*data*, *scale=1.0*, *offset=0.0*)

Copies pixel data to this image. This method copies data from a sequence object into the image, starting at the upper left corner (0, 0), and continuing until either the image or the sequence ends. The scale and offset values are used to adjust the sequence values: **pixel = value*scale + offset**.

Parameters

- **data** – A sequence object.
- **scale** – An optional scale value. The default is 1.0.
- **offset** – An optional offset value. The default is 0.0.

Image.**putpalette** (*data*, *rawmode*='RGB')

Attaches a palette to this image. The image must be a “P”, “PA”, “L” or “LA” image, and the palette sequence must contain 768 integer values, where each group of three values represent the red, green, and blue values for the corresponding pixel index. Instead of an integer sequence, you can use an 8-bit string.

Parameters

- **data** – A palette sequence (either a list or a string).
- **rawmode** – The raw mode of the palette.

Image.**putpixel** (*xy*, *value*)

Modifies the pixel at the given position. The color is given as a single numerical value for single-band images, and a tuple for multi-band images. In addition to this, RGB and RGBA tuples are accepted for P images.

Note that this method is relatively slow. For more extensive changes, use *paste()* or the *ImageDraw* module instead.

See:

- *paste()*
- *putdata()*
- *ImageDraw*

Parameters

- **xy** – The pixel coordinate, given as (x, y). See *Coordinate System*.
- **value** – The pixel value.

Image.**quantize** (*colors*=256, *method*=None, *kmeans*=0, *palette*=None, *dither*=1)

Convert the image to ‘P’ mode with the specified number of colors.

Parameters

- **colors** – The desired number of colors, <= 256
- **method** – 0 = median cut 1 = maximum coverage 2 = fast octree 3 = libimagequant
- **kmeans** – Integer
- **palette** – Quantize to the palette of given *PIL.Image.Image*.
- **dither** – Dithering method, used when converting from mode “RGB” to “P” or from “RGB” or “L” to “1”. Available methods are NONE or FLOYDSTEINBERG (default). Default: 1 (legacy setting)

Returns A new image

Image.**resize** (*size*, *resample*=3, *box*=None, *reducing_gap*=None)

Returns a resized copy of this image.

Parameters

- **size** – The requested size in pixels, as a 2-tuple: (width, height).

- **resample** – An optional resampling filter. This can be one of `PIL.Image.NEAREST`, `PIL.Image.BOX`, `PIL.Image.BILINEAR`, `PIL.Image.HAMMING`, `PIL.Image.BICUBIC` or `PIL.Image.LANCZOS`. Default filter is `PIL.Image.BICUBIC`. If the image has mode “1” or “P”, it is always set to `PIL.Image.NEAREST`. See: *Filters*.
- **box** – An optional 4-tuple of floats providing the source image region to be scaled. The values must be within (0, 0, width, height) rectangle. If omitted or `None`, the entire source is used.
- **reducing_gap** – Apply optimization by resizing the image in two steps. First, reducing the image by integer times using `reduce()`. Second, resizing using regular resampling. The last step changes size no less than by `reducing_gap` times. `reducing_gap` may be `None` (no first step is performed) or should be greater than 1.0. The bigger `reducing_gap`, the closer the result to the fair resampling. The smaller `reducing_gap`, the faster resizing. With `reducing_gap` greater or equal to 3.0, the result is indistinguishable from fair resampling in most cases. The default value is `None` (no optimization).

Returns An *Image* object.

This resizes the given image from (width, height) to (width/2, height/2):

```
from PIL import Image

im = Image.open("hopper.jpg")

# Provide the target width and height of the image
(width, height) = (im.width // 2, im.height // 2)
im_resized = im.resize((width, height))
```

`Image.remapped_palette` (*dest_map*, *source_palette=None*)

Rewrites the image to reorder the palette.

Parameters

- **dest_map** – A list of indexes into the original palette. e.g. [1,0] would swap a two item palette, and `list(range(256))` is the identity transform.
- **source_palette** – Bytes or `None`.

Returns An *Image* object.

`Image.rotate` (*angle*, *resample=0*, *expand=0*, *center=None*, *translate=None*, *fillcolor=None*)

Returns a rotated copy of this image. This method returns a copy of this image, rotated the given number of degrees counter clockwise around its centre.

Parameters

- **angle** – In degrees counter clockwise.
- **resample** – An optional resampling filter. This can be one of `PIL.Image.NEAREST` (use nearest neighbour), `PIL.Image.BILINEAR` (linear interpolation in a 2x2 environment), or `PIL.Image.BICUBIC` (cubic spline interpolation in a 4x4 environment). If omitted, or if the image has mode “1” or “P”, it is set to `PIL.Image.NEAREST`. See *Filters*.
- **expand** – Optional expansion flag. If true, expands the output image to make it large enough to hold the entire rotated image. If false or omitted, make the output image the same size as the input image. Note that the expand flag assumes rotation around the center and no translation.

- **center** – Optional center of rotation (a 2-tuple). Origin is the upper left corner. Default is the center of the image.
- **translate** – An optional post-rotate translation (a 2-tuple).
- **fillcolor** – An optional color for area outside the rotated image.

Returns An *Image* object.

This rotates the input image by `theta` degrees counter clockwise:

```
from PIL import Image

im = Image.open("hopper.jpg")

# Rotate the image by 60 degrees counter clockwise
theta = 60
# Angle is in degrees counter clockwise
im_rotated = im.rotate(angle=theta)
```

`Image.save` (*fp*, *format=None*, ***params*)

Saves this image under the given filename. If no format is specified, the format to use is determined from the filename extension, if possible.

Keyword options can be used to provide additional instructions to the writer. If a writer doesn't recognise an option, it is silently ignored. The available options are described in the *image format documentation* for each writer.

You can use a file object instead of a filename. In this case, you must always specify the format. The file object must implement the `seek`, `tell`, and `write` methods, and be opened in binary mode.

Parameters

- **fp** – A filename (string), `pathlib.Path` object or file object.
- **format** – Optional format override. If omitted, the format to use is determined from the filename extension. If a file object was used instead of a filename, this parameter should always be used.
- **params** – Extra parameters to the image writer.

Returns None

Raises

- **ValueError** – If the output format could not be determined from the file name. Use the `format` option to solve this.
- **IOError** – If the file could not be written. The file may have been created, and may contain partial data.

`Image.seek` (*frame*)

Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method raises an **EOFError** exception. When a sequence file is opened, the library automatically seeks to frame 0.

See `tell()`.

Parameters **frame** – Frame number, starting at 0.

Raises **EOFError** – If the call attempts to seek beyond the end of the sequence.

`Image.show` (*title=None*, *command=None*)

Displays this image. This method is mainly intended for debugging purposes.

The image is first saved to a temporary file. By default, it will be in PNG format.

On Unix, the image is then opened using the **display**, **eog** or **xv** utility, depending on which one can be found.

On macOS, the image is opened with the native Preview application.

On Windows, the image is opened with the standard PNG display utility.

Parameters

- **title** – Optional title to use for the image window, where possible.
- **command** – command used to show the image

`Image.split()`

Split this image into individual bands. This method returns a tuple of individual image bands from an image. For example, splitting an “RGB” image creates three new images each containing a copy of one of the original bands (red, green, blue).

If you need only one band, `getchannel()` method can be more convenient and faster.

Returns A tuple containing bands.

`Image.getchannel(channel)`

Returns an image containing a single channel of the source image.

Parameters **channel** – What channel to return. Could be index (0 for “R” channel of “RGB”) or channel name (“A” for alpha channel of “RGBA”).

Returns An image in “L” mode.

New in version 4.3.0.

`Image.tell()`

Returns the current frame number. See `seek()`.

Returns Frame number, starting with 0.

`Image.thumbnail(size, resample=3, reducing_gap=2.0)`

Make this image into a thumbnail. This method modifies the image to contain a thumbnail version of itself, no larger than the given size. This method calculates an appropriate thumbnail size to preserve the aspect of the image, calls the `draft()` method to configure the file reader (where applicable), and finally resizes the image.

Note that this function modifies the `Image` object in place. If you need to use the full resolution image as well, apply this method to a `copy()` of the original image.

Parameters

- **size** – Requested size.
- **resample** – Optional resampling filter. This can be one of `PIL.Image.NEAREST`, `PIL.Image.BILINEAR`, `PIL.Image.BICUBIC`, or `PIL.Image.LANCZOS`. If omitted, it defaults to `PIL.Image.BICUBIC`. (was `PIL.Image.NEAREST` prior to version 2.5.0).
- **reducing_gap** – Apply optimization by resizing the image in two steps. First, reducing the image by integer times using `reduce()` or `draft()` for JPEG images. Second, resizing using regular resampling. The last step changes size no less than by `reducing_gap` times. `reducing_gap` may be `None` (no first step is performed) or should be greater than 1.0. The bigger `reducing_gap`, the closer the result to the fair resampling. The smaller `reducing_gap`, the faster resizing. With `reducing_gap` greater or equal to 3.0, the result is indistinguishable from fair resampling in most cases. The default value is 2.0 (very close to fair resampling while still being faster in many cases).

Returns `None`

`Image.tobitmap` (*name='image'*)
Returns the image converted to an X11 bitmap.

Note: This method only works for mode “1” images.

Parameters *name* – The name prefix to use for the bitmap variables.

Returns A string containing an X11 bitmap.

Raises `ValueError` – If the mode is not “1”

`Image.tobytes` (*encoder_name='raw', *args*)
Return image as a bytes object.

Warning: This method returns the raw image data from the internal storage. For compressed image data (e.g. PNG, JPEG) use `save()`, with a `BytesIO` parameter for in-memory data.

Parameters

- **encoder_name** – What encoder to use. The default is to use the standard “raw” encoder.
- **args** – Extra arguments to the encoder.

Return type A bytes object.

`Image.tostring` (**args, **kw*)

`Image.transform` (*size, method, data=None, resample=0, fill=1, fillcolor=None*)
Transforms this image. This method creates a new image with the given size, and the same mode as the original, and copies data to the new image using the given transform.

Parameters

- **size** – The output size.
- **method** – The transformation method. This is one of `PIL.Image.EXTENT` (cut out a rectangular subregion), `PIL.Image.AFFINE` (affine transform), `PIL.Image.PERSPECTIVE` (perspective transform), `PIL.Image.QUAD` (map a quadrilateral to a rectangle), or `PIL.Image.MESH` (map a number of source quadrilaterals in one operation).

It may also be an `ImageTransformHandler` object:

```
class Example(Image.ImageTransformHandler):
    def transform(size, method, data, resample, fill=1):
        # Return result
```

It may also be an object with a `getdata()` method that returns a tuple supplying new **method** and **data** values:

```
class Example(object):
    def getdata(self):
        method = Image.EXTENT
        data = (0, 0, 100, 100)
        return method, data
```

- **data** – Extra data to the transformation method.

- **resample** – Optional resampling filter. It can be one of `PIL.Image.NEAREST` (use nearest neighbour), `PIL.Image.BILINEAR` (linear interpolation in a 2x2 environment), or `PIL.Image.BICUBIC` (cubic spline interpolation in a 4x4 environment). If omitted, or if the image has mode “1” or “P”, it is set to `PIL.Image.NEAREST`.
- **fill** – If **method** is an `ImageTransformHandler` object, this is one of the arguments passed to it. Otherwise, it is unused.
- **fillcolor** – Optional fill color for the area outside the transform in the output image.

Returns An *Image* object.

`Image.transpose` (*method*)

Transpose image (flip or rotate in 90 degree steps)

Parameters method – One of `PIL.Image.FLIP_LEFT_RIGHT`, `PIL.Image.FLIP_TOP_BOTTOM`, `PIL.Image.ROTATE_90`, `PIL.Image.ROTATE_180`, `PIL.Image.ROTATE_270`, `PIL.Image.TRANSPOSE` or `PIL.Image.TRANSVERSE`.

Returns Returns a flipped or rotated copy of this image.

This flips the input image by using the `Image.FLIP_LEFT_RIGHT` method.

```
from PIL import Image

im = Image.open("hopper.jpg")

# Flip the image from left to right
im_flipped = im.transpose(method=Image.FLIP_LEFT_RIGHT)
# To flip the image from top to bottom,
# use the method "Image.FLIP_TOP_BOTTOM"
```

`Image.verify` ()

Verifies the contents of a file. For data read from a file, this method attempts to determine if the file is broken, without actually decoding the image data. If this method finds any problems, it raises suitable exceptions. If you need to load the image after using this method, you must reopen the image file.

`Image.fromstring` (*args, **kw)

`Image.load` ()

Allocates storage for the image and loads the pixel data. In normal cases, you don’t need to call this method, since the `Image` class automatically loads an opened image when it is accessed for the first time.

If the file associated with the image was opened by Pillow, then this method will close it. The exception to this is if the image has multiple frames, in which case the file will be left open for seek operations. See *File Handling in Pillow* for more information.

Returns An image access object.

Return type *PixelAccess Class* or *PIL.PyAccess*

`Image.close` ()

Closes the file pointer, if possible.

This operation will destroy the image core and release its memory. The image data will be unusable afterward.

This function is only required to close images that have not had their file read and closed by the `load()` method. See *File Handling in Pillow* for more information.

3.1.4 Attributes

Instances of the *Image* class have the following attributes:

PIL.Image.filename

The filename or path of the source file. Only images created with the factory function `open` have a filename attribute. If the input is a file like object, the filename attribute is set to an empty string.

Type `string`

PIL.Image.format

The file format of the source file. For images created by the library itself (via a factory function, or by running a method on an existing image), this attribute is set to `None`.

Type `string` or `None`

PIL.Image.mode

Image mode. This is a string specifying the pixel format used by the image. Typical values are “1”, “L”, “RGB”, or “CMYK.” See *Modes* for a full list.

Type `string`

PIL.Image.size

Image size, in pixels. The size is given as a 2-tuple (width, height).

Type `(width, height)`

PIL.Image.width

Image width, in pixels.

Type `int`

PIL.Image.height

Image height, in pixels.

Type `int`

PIL.Image.palette

Colour palette table, if any. If mode is “P” or “PA”, this should be an instance of the *ImagePalette* class. Otherwise, it should be set to `None`.

Type *ImagePalette* or `None`

PIL.Image.info

A dictionary holding data associated with the image. This dictionary is used by file handlers to pass on various non-image information read from the file. See documentation for the various file handlers for details.

Most methods ignore the dictionary when returning new images; since the keys are not standardized, it’s not possible for a method to know if the operation affects the dictionary. If you need the information later on, keep a reference to the info dictionary returned from the `open` method.

Unless noted elsewhere, this dictionary does not affect saving files.

Type `dict`

3.2 ImageChops (“Channel Operations”) Module

The *ImageChops* module contains a number of arithmetical image operations, called channel operations (“chops”). These can be used for various purposes, including special effects, image compositions, algorithmic painting, and more.

For more pre-made operations, see *ImageOps*.

At this time, most channel operations are only implemented for 8-bit images (e.g. “L” and “RGB”).

3.2.1 Functions

Most channel operations take one or two image arguments and returns a new image. Unless otherwise noted, the result of a channel operation is always clipped to the range 0 to MAX (which is 255 for all modes supported by the operations in this module).

`PIL.ImageChops.add` (*image1*, *image2*, *scale=1.0*, *offset=0*)

Adds two images, dividing the result by scale and adding the offset. If omitted, scale defaults to 1.0, and offset to 0.0. At least one of the images must have mode “1”.

```
out = ((image1 + image2) / scale + offset)
```

Return type *Image*

`PIL.ImageChops.add_modulo` (*image1*, *image2*)

Add two images, without clipping the result. At least one of the images must have mode “1”.

```
out = ((image1 + image2) % MAX)
```

Return type *Image*

`PIL.ImageChops.blend` (*image1*, *image2*, *alpha*)

Blend images using constant transparency weight. Alias for `PIL.Image.Image.blend()`.

Return type *Image*

`PIL.ImageChops.composite` (*image1*, *image2*, *mask*)

Create composite using transparency mask. Alias for `PIL.Image.Image.composite()`.

Return type *Image*

`PIL.ImageChops.constant` (*image*, *value*)

Fill a channel with a given grey level.

Return type *Image*

`PIL.ImageChops.darker` (*image1*, *image2*)

Compares the two images, pixel by pixel, and returns a new image containing the darker values. At least one of the images must have mode “1”.

```
out = min(image1, image2)
```

Return type *Image*

`PIL.ImageChops.difference` (*image1*, *image2*)

Returns the absolute value of the pixel-by-pixel difference between the two images. At least one of the images must have mode “1”.

```
out = abs(image1 - image2)
```

Return type *Image*

`PIL.ImageChops.duplicate` (*image*)

Copy a channel. Alias for `PIL.Image.Image.copy()`.

Return type *Image*

`PIL.ImageChops.invert` (*image*)
Invert an image (channel).

```
out = MAX - image
```

Return type *Image*

`PIL.ImageChops.lighter` (*image1*, *image2*)
Compares the two images, pixel by pixel, and returns a new image containing the lighter values. At least one of the images must have mode “1”.

```
out = max(image1, image2)
```

Return type *Image*

`PIL.ImageChops.logical_and` (*image1*, *image2*)
Logical AND between two images. At least one of the images must have mode “1”.

```
out = ((image1 and image2) % MAX)
```

Return type *Image*

`PIL.ImageChops.logical_or` (*image1*, *image2*)
Logical OR between two images. At least one of the images must have mode “1”.

```
out = ((image1 or image2) % MAX)
```

Return type *Image*

`PIL.ImageChops.logical_xor` (*image1*, *image2*)
Logical XOR between two images. At least one of the images must have mode “1”.

```
out = ((bool(image1) != bool(image2)) % MAX)
```

Return type *Image*

`PIL.ImageChops.multiply` (*image1*, *image2*)
Superimposes two images on top of each other.

If you multiply an image with a solid black image, the result is black. If you multiply with a solid white image, the image is unaffected. At least one of the images must have mode “1”.

```
out = image1 * image2 / MAX
```

Return type *Image*

`PIL.ImageChops.soft_light` (*image1*, *image2*)
Superimposes two images on top of each other using the Soft Light algorithm

Return type *Image*

`PIL.ImageChops.hard_light` (*image1*, *image2*)
Superimposes two images on top of each other using the Hard Light algorithm

Return type *Image*

`PIL.ImageChops.overlay` (*image1*, *image2*)
Superimposes two images on top of each other using the Overlay algorithm

Return type *Image*

`PIL.ImageChops.offset` (*image*, *xoffset*, *yoffset=None*)
Returns a copy of the image where data has been offset by the given distances. Data wraps around the edges. If *yoffset* is omitted, it is assumed to be equal to *xoffset*.

`PIL.ImageChops.screen` (*image1*, *image2*)
Superimposes two inverted images on top of each other. At least one of the images must have mode “1”.

```
out = MAX - ((MAX - image1) * (MAX - image2) / MAX)
```

Return type *Image*

`PIL.ImageChops.subtract` (*image1*, *image2*, *scale=1.0*, *offset=0*)
Subtracts two images, dividing the result by *scale* and adding the *offset*. If omitted, *scale* defaults to 1.0, and *offset* to 0.0. At least one of the images must have mode “1”.

```
out = ((image1 - image2) / scale + offset)
```

Return type *Image*

`PIL.ImageChops.subtract_modulo` (*image1*, *image2*)
Subtract two images, without clipping the result. At least one of the images must have mode “1”.

```
out = ((image1 - image2) % MAX)
```

Return type *Image*

3.3 ImageColor Module

The `ImageColor` module contains color tables and converters from CSS3-style color specifiers to RGB tuples. This module is used by `PIL.Image.new()` and the `ImageDraw` module, among others.

3.3.1 Color Names

The `ImageColor` module supports the following string formats:

- Hexadecimal color specifiers, given as `#rgb` or `#rrggbb`. For example, `#ff0000` specifies pure red.
- RGB functions, given as `rgb(red, green, blue)` where the color values are integers in the range 0 to 255. Alternatively, the color values can be given as three percentages (0% to 100%). For example, `rgb(255, 0, 0)` and `rgb(100%, 0%, 0%)` both specify pure red.
- Hue-Saturation-Lightness (HSL) functions, given as `hsl(hue, saturation%, lightness%)` where *hue* is the color given as an angle between 0 and 360 (red=0, green=120, blue=240), *saturation* is a value between 0% and 100% (gray=0%, full color=100%), and *lightness* is a value between 0% and 100% (black=0%, normal=50%, white=100%). For example, `hsl(0, 100%, 50%)` is pure red.

- Hue-Saturation-Value (HSV) functions, given as `hsv(hue, saturation%, value%)` where hue and saturation are the same as HSL, and value is between 0% and 100% (black=0%, normal=100%). For example, `hsv(0, 100%, 100%)` is pure red. This format is also known as Hue-Saturation-Brightness (HSB), and can be given as `hsb(hue, saturation%, brightness%)`, where each of the values are used as they are in HSV.
- Common HTML color names. The `ImageColor` module provides some 140 standard color names, based on the colors supported by the X Window system and most web browsers. color names are case insensitive. For example, `red` and `Red` both specify pure red.

3.3.2 Functions

`PIL.ImageColor.getrgb(color)`

Convert a color string to an RGB tuple. If the string cannot be parsed, this function raises a `ValueError` exception.

New in version 1.1.4.

`PIL.ImageColor.getcolor(color, mode)`

Same as `getrgb()`, but converts the RGB value to a greyscale value if the mode is not color or a palette image. If the string cannot be parsed, this function raises a `ValueError` exception.

New in version 1.1.4.

3.4 ImageCms Module

The `ImageCms` module provides color profile management support using the LittleCMS2 color management engine, based on Kevin Cazabon's PyCMS library.

class `PIL.ImageCms.ImageCmsTransform(input, output, input_mode, output_mode, intent=0, proof=None, proof_intent=3, flags=0)`

Transform. This can be used with the procedural API, or with the standard `Image.point()` method.

Will return the output profile in the `output.info['icc_profile']`.

exception `PIL.ImageCms.PyCMSError`

(pyCMS) Exception class. This is used for all errors in the pyCMS API.

`PIL.ImageCms.applyTransform(im, transform, inPlace=False)`

(pyCMS) Applies a transform to a given image.

If `im.mode != transform.inMode`, a `PyCMSError` is raised.

If `inPlace` is `True` and `transform.inMode != transform.outMode`, a `PyCMSError` is raised.

If `im.mode`, `transform.inMode`, or `transform.outMode` is not supported by `pyCMSdll` or the profiles you used for the transform, a `PyCMSError` is raised.

If an error occurs while the transform is being applied, a `PyCMSError` is raised.

This function applies a pre-calculated transform (from `ImageCms.buildTransform()` or `ImageCms.buildTransformFromOpenProfiles()`) to an image. The transform can be used for multiple images, saving considerable calculation time if doing the same conversion multiple times.

If you want to modify `im` in-place instead of receiving a new image as the return value, set `inPlace` to `True`. This can only be done if `transform.inMode` and `transform.outMode` are the same, because we can't change the mode in-place (the buffer sizes for some modes are different). The default behavior is to return a new `Image` object of the same dimensions in mode `transform.outMode`.

Parameters

- **im** – A PIL Image object, and im.mode must be the same as the inMode supported by the transform.
- **transform** – A valid CmsTransform class object
- **inPlace** – Bool. If True, im is modified in place and None is returned, if False, a new Image object with the transform applied is returned (and im is not changed). The default is False.

Returns Either None, or a new PIL Image object, depending on the value of inPlace. The profile will be returned in the image’s info[‘icc_profile’].

Raises **PyCMSError** –

`PIL.ImageCms.buildProofTransform(inputProfile, outputProfile, proofProfile, inMode, outMode, renderingIntent=0, proofRenderingIntent=3, flags=16384)`
(pyCMS) Builds an ICC transform mapping from the inputProfile to the outputProfile, but tries to simulate the result that would be obtained on the proofProfile device.

If the input, output, or proof profiles specified are not valid filenames, a PyCMSError will be raised.

If an error occurs during creation of the transform, a PyCMSError will be raised.

If inMode or outMode are not a mode supported by the outputProfile (or by pyCMS), a PyCMSError will be raised.

This function builds and returns an ICC transform from the inputProfile to the outputProfile, but tries to simulate the result that would be obtained on the proofProfile device using renderingIntent and proofRenderingIntent to determine what to do with out-of-gamut colors. This is known as “soft-proofing”. It will ONLY work for converting images that are in inMode to images that are in outMode color format (PIL mode, i.e. “RGB”, “RGBA”, “CMYK”, etc.).

Usage of the resulting transform object is exactly the same as with ImageCms.buildTransform().

Proof profiling is generally used when using an output device to get a good idea of what the final printed/displayed image would look like on the proofProfile device when it’s quicker and easier to use the output device for judging color. Generally, this means that the output device is a monitor, or a dye-sub printer (etc.), and the simulated device is something more expensive, complicated, or time consuming (making it difficult to make a real print for color judgement purposes).

Soft-proofing basically functions by adjusting the colors on the output device to match the colors of the device being simulated. However, when the simulated device has a much wider gamut than the output device, you may obtain marginal results.

Parameters

- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this transform, or a profile object
- **outputProfile** – String, as a valid filename path to the ICC output (monitor, usually) profile you wish to use for this transform, or a profile object
- **proofProfile** – String, as a valid filename path to the ICC proof profile you wish to use for this transform, or a profile object
- **inMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **outMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)

- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the input->proof (simulated) transform

```
ImageCms.INTENT_PERCEPTUAL      =      0      (DEFAULT)
ImageCms.INTENT_RELATIVE_COLORIMETRIC      =
1      ImageCms.INTENT_SATURATION      =      2      Im-
ageCms.INTENT_ABSOLUTE_COLORIMETRIC = 3
```

see the pyCMS documentation for details on rendering intents and what they do.

- **proofRenderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for proof->output transform

```
ImageCms.INTENT_PERCEPTUAL      =      0      (DEFAULT)
ImageCms.INTENT_RELATIVE_COLORIMETRIC      =
1      ImageCms.INTENT_SATURATION      =      2      Im-
ageCms.INTENT_ABSOLUTE_COLORIMETRIC = 3
```

see the pyCMS documentation for details on rendering intents and what they do.

- **flags** – Integer (0-...) specifying additional flags

Returns A CmsTransform class object.

Raises **PyCMSError** –

`PIL.ImageCms.buildProofTransformFromOpenProfiles` (*inputProfile*, *outputProfile*, *proofProfile*, *inMode*, *outMode*, *renderingIntent=0*, *proofRenderingIntent=3*, *flags=16384*)

(pyCMS) Builds an ICC transform mapping from the inputProfile to the outputProfile, but tries to simulate the result that would be obtained on the proofProfile device.

If the input, output, or proof profiles specified are not valid filenames, a PyCMSError will be raised.

If an error occurs during creation of the transform, a PyCMSError will be raised.

If inMode or outMode are not a mode supported by the outputProfile (or by pyCMS), a PyCMSError will be raised.

This function builds and returns an ICC transform from the inputProfile to the outputProfile, but tries to simulate the result that would be obtained on the proofProfile device using renderingIntent and proofRenderingIntent to determine what to do with out-of-gamut colors. This is known as “soft-proofing”. It will ONLY work for converting images that are in inMode to images that are in outMode color format (PIL mode, i.e. “RGB”, “RGBA”, “CMYK”, etc.).

Usage of the resulting transform object is exactly the same as with ImageCms.buildTransform().

Proof profiling is generally used when using an output device to get a good idea of what the final printed/displayed image would look like on the proofProfile device when it’s quicker and easier to use the output device for judging color. Generally, this means that the output device is a monitor, or a dye-sub printer (etc.), and the simulated device is something more expensive, complicated, or time consuming (making it difficult to make a real print for color judgement purposes).

Soft-proofing basically functions by adjusting the colors on the output device to match the colors of the device being simulated. However, when the simulated device has a much wider gamut than the output device, you may obtain marginal results.

Parameters

- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this transform, or a profile object

- **outputProfile** – String, as a valid filename path to the ICC output (monitor, usually) profile you wish to use for this transform, or a profile object
- **proofProfile** – String, as a valid filename path to the ICC proof profile you wish to use for this transform, or a profile object
- **inMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **outMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the input->proof (simulated) transform

```
ImageCms.INTENT_PERCEPTUAL          =          0          (DEFAULT)
ImageCms.INTENT_RELATIVE_COLORIMETRIC =          =
1      ImageCms.INTENT_SATURATION      =          2      Im-
imageCms.INTENT_ABSOLUTE_COLORIMETRIC = 3
```

see the pyCMS documentation for details on rendering intents and what they do.

- **proofRenderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for proof->output transform

```
ImageCms.INTENT_PERCEPTUAL          =          0          (DEFAULT)
ImageCms.INTENT_RELATIVE_COLORIMETRIC =          =
1      ImageCms.INTENT_SATURATION      =          2      Im-
imageCms.INTENT_ABSOLUTE_COLORIMETRIC = 3
```

see the pyCMS documentation for details on rendering intents and what they do.

- **flags** – Integer (0-...) specifying additional flags

Returns A CmsTransform class object.

Raises PyCMSError –

PIL. ImageCms.**buildTransform**(*inputProfile*, *outputProfile*, *inMode*, *outMode*, *renderingIntent=0*, *flags=0*)

(pyCMS) Builds an ICC transform mapping from the inputProfile to the outputProfile. Use applyTransform to apply the transform to a given image.

If the input or output profiles specified are not valid filenames, a PyCMSError will be raised. If an error occurs during creation of the transform, a PyCMSError will be raised.

If inMode or outMode are not a mode supported by the outputProfile (or by pyCMS), a PyCMSError will be raised.

This function builds and returns an ICC transform from the inputProfile to the outputProfile using the rendering-Intent to determine what to do with out-of-gamut colors. It will ONLY work for converting images that are in inMode to images that are in outMode color format (PIL mode, i.e. “RGB”, “RGBA”, “CMYK”, etc.).

Building the transform is a fair part of the overhead in ImageCms.profileToProfile(), so if you’re planning on converting multiple images using the same input/output settings, this can save you time. Once you have a transform object, it can be used with ImageCms.applyProfile() to convert images without the need to re-compute the lookup table for the transform.

The reason pyCMS returns a class object rather than a handle directly to the transform is that it needs to keep track of the PIL input/output modes that the transform is meant for. These attributes are stored in the “inMode” and “outMode” attributes of the object (which can be manually overridden if you really want to, but I don’t know of any time that would be of use, or would even work).

Parameters

- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this transform, or a profile object
- **outputProfile** – String, as a valid filename path to the ICC output profile you wish to use for this transform, or a profile object
- **inMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **outMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the transform

```
ImageCms.INTENT_PERCEPTUAL          =          0          (DEFAULT)
ImageCms.INTENT_RELATIVE_COLORIMETRIC =          1          =
1          ImageCms.INTENT_SATURATION  =          2          Im-
ageCms.INTENT_ABSOLUTE_COLORIMETRIC = 3
```

see the pyCMS documentation for details on rendering intents and what they do.

- **flags** – Integer (0-...) specifying additional flags

Returns A CmsTransform class object.

Raises **PyCMSError** –

`PIL.ImageCms.buildTransformFromOpenProfiles` (*inputProfile*, *outputProfile*, *inMode*, *outMode*, *renderingIntent=0*, *flags=0*)

(pyCMS) Builds an ICC transform mapping from the *inputProfile* to the *outputProfile*. Use `applyTransform` to apply the transform to a given image.

If the input or output profiles specified are not valid filenames, a `PyCMSError` will be raised. If an error occurs during creation of the transform, a `PyCMSError` will be raised.

If *inMode* or *outMode* are not a mode supported by the *outputProfile* (or by pyCMS), a `PyCMSError` will be raised.

This function builds and returns an ICC transform from the *inputProfile* to the *outputProfile* using the *renderingIntent* to determine what to do with out-of-gamut colors. It will ONLY work for converting images that are in *inMode* to images that are in *outMode* color format (PIL mode, i.e. “RGB”, “RGBA”, “CMYK”, etc.).

Building the transform is a fair part of the overhead in `ImageCms.profileToProfile()`, so if you’re planning on converting multiple images using the same input/output settings, this can save you time. Once you have a transform object, it can be used with `ImageCms.applyProfile()` to convert images without the need to re-compute the lookup table for the transform.

The reason pyCMS returns a class object rather than a handle directly to the transform is that it needs to keep track of the PIL input/output modes that the transform is meant for. These attributes are stored in the “*inMode*” and “*outMode*” attributes of the object (which can be manually overridden if you really want to, but I don’t know of any time that would be of use, or would even work).

Parameters

- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this transform, or a profile object
- **outputProfile** – String, as a valid filename path to the ICC output profile you wish to use for this transform, or a profile object
- **inMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)

- **outMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the transform

```
ImageCms.INTENT_PERCEPTUAL          =          0          (DEFAULT)
ImageCms.INTENT_RELATIVE_COLORIMETRIC =
1          ImageCms.INTENT_SATURATION =          2          Im-
ageCms.INTENT_ABSOLUTE_COLORIMETRIC = 3
```

see the pyCMS documentation for details on rendering intents and what they do.

- **flags** – Integer (0-...) specifying additional flags

Returns A CmsTransform class object.

Raises PyCMSError –

PIL. ImageCms.**createProfile** (*colorSpace*, *colorTemp=-1*)
(pyCMS) Creates a profile.

If colorSpace not in [“LAB”, “XYZ”, “sRGB”], a PyCMSError is raised

If using LAB and colorTemp != a positive integer, a PyCMSError is raised.

If an error occurs while creating the profile, a PyCMSError is raised.

Use this function to create common profiles on-the-fly instead of having to supply a profile on disk and knowing the path to it. It returns a normal CmsProfile object that can be passed to ImageCms.buildTransformFromOpenProfiles() to create a transform to apply to images.

Parameters

- **colorSpace** – String, the color space of the profile you wish to create. Currently only “LAB”, “XYZ”, and “sRGB” are supported.
- **colorTemp** – Positive integer for the white point for the profile, in degrees Kelvin (i.e. 5000, 6500, 9600, etc.). The default is for D50 illuminant if omitted (5000k). colorTemp is ONLY applied to LAB profiles, and is ignored for XYZ and sRGB.

Returns A CmsProfile class object

Raises PyCMSError –

PIL. ImageCms.**getDefaultIntent** (*profile*)
(pyCMS) Gets the default intent name for the given profile.

If profile isn’t a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the default intent, a PyCMSError is raised.

Use this function to determine the default (and usually best optimized) rendering intent for this profile. Most profiles support multiple rendering intents, but are intended mostly for one type of conversion. If you wish to use a different intent than returned, use ImageCms.isIntentSupported() to verify it will work first.

Parameters profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

Returns

Integer 0-3 specifying the default rendering intent for this profile.

```

ImageCms.INTENT_PERCEPTUAL      = 0      (DEFAULT)      Im-
ageCms.INTENT_RELATIVE_COLORIMETRIC  = 1      Im-
ageCms.INTENT_SATURATION = 2 ImageCms.INTENT_ABSOLUTE_COLORIMETRIC
= 3

```

see the pyCMS documentation for details on rendering intents and what they do.

Raises PyCMSError –

PIL. ImageCms.**getOpenProfile** (*profileFilename*)
(pyCMS) Opens an ICC profile file.

The PyCMSProfile object can be passed back into pyCMS for use in creating transforms and such (as in ImageCms.buildTransformFromOpenProfiles()).

If profileFilename is not a valid filename for an ICC profile, a PyCMSError will be raised.

Parameters profileFilename – String, as a valid filename path to the ICC profile you wish to open, or a file-like object.

Returns A CmsProfile class object.

Raises PyCMSError –

PIL. ImageCms.**getProfileCopyright** (*profile*)
(pyCMS) Gets the copyright for the given profile.

If profile isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the copyright tag, a PyCMSError is raised

Use this function to obtain the information stored in the profile's copyright tag.

Parameters profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

Returns A string containing the internal profile information stored in an ICC tag.

Raises PyCMSError –

PIL. ImageCms.**getProfileDescription** (*profile*)
(pyCMS) Gets the description for the given profile.

If profile isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the description tag, a PyCMSError is raised

Use this function to obtain the information stored in the profile's description tag.

Parameters profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

Returns A string containing the internal profile information stored in an ICC tag.

Raises PyCMSError –

PIL. ImageCms.**getProfileInfo** (*profile*)
(pyCMS) Gets the internal product information for the given profile.

If profile isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the info tag, a PyCMSError is raised

Use this function to obtain the information stored in the profile's info tag. This often contains details about the profile, and how it was created, as supplied by the creator.

Parameters `profile` – EITHER a valid `CmsProfile` object, OR a string of the filename of an ICC profile.

Returns A string containing the internal profile information stored in an ICC tag.

Raises `PyCMSError` –

`PIL.ImageCms.getProfileManufacturer` (*profile*)
(pyCMS) Gets the manufacturer for the given profile.

If `profile` isn't a valid `CmsProfile` object or filename to a profile, a `PyCMSError` is raised.

If an error occurs while trying to obtain the manufacturer tag, a `PyCMSError` is raised

Use this function to obtain the information stored in the profile's manufacturer tag.

Parameters `profile` – EITHER a valid `CmsProfile` object, OR a string of the filename of an ICC profile.

Returns A string containing the internal profile information stored in an ICC tag.

Raises `PyCMSError` –

`PIL.ImageCms.getProfileModel` (*profile*)
(pyCMS) Gets the model for the given profile.

If `profile` isn't a valid `CmsProfile` object or filename to a profile, a `PyCMSError` is raised.

If an error occurs while trying to obtain the model tag, a `PyCMSError` is raised

Use this function to obtain the information stored in the profile's model tag.

Parameters `profile` – EITHER a valid `CmsProfile` object, OR a string of the filename of an ICC profile.

Returns A string containing the internal profile information stored in an ICC tag.

Raises `PyCMSError` –

`PIL.ImageCms.getProfileName` (*profile*)
(pyCMS) Gets the internal product name for the given profile.

If `profile` isn't a valid `CmsProfile` object or filename to a profile, a `PyCMSError` is raised If an error occurs while trying to obtain the name tag, a `PyCMSError` is raised.

Use this function to obtain the INTERNAL name of the profile (stored in an ICC tag in the profile itself), usually the one used when the profile was originally created. Sometimes this tag also contains additional information supplied by the creator.

Parameters `profile` – EITHER a valid `CmsProfile` object, OR a string of the filename of an ICC profile.

Returns A string containing the internal name of the profile as stored in an ICC tag.

Raises `PyCMSError` –

`PIL.ImageCms.get_display_profile` (*handle=None*)
(experimental) Fetches the profile for the current display device. :returns: None if the profile is not known.

`PIL.ImageCms.isIntentSupported` (*profile, intent, direction*)
(pyCMS) Checks if a given intent is supported.

Use this function to verify that you can use your desired `renderingIntent` with `profile`, and that `profile` can be used for the `input/output/proof` profile as you desire.

Some profiles are created specifically for one "direction", can cannot be used for others. Some profiles can only be used for certain rendering intents... so it's best to either verify this before trying to create a transform with

them (using this function), or catch the potential `PyCMSError` that will occur if they don't support the modes you select.

Parameters

- **profile** – EITHER a valid `CmsProfile` object, OR a string of the filename of an ICC profile.
- **intent** – Integer (0-3) specifying the rendering intent you wish to use with this profile

<code>ImageCms.INTENT_PERCEPTUAL</code>	=	0	(DEFAULT)
<code>ImageCms.INTENT_RELATIVE_COLORIMETRIC</code>	=	1	
<code>ImageCms.INTENT_SATURATION</code>	=	2	Im-
<code>ImageCms.INTENT_ABSOLUTE_COLORIMETRIC</code>	=	3	

see the `pyCMS` documentation for details on rendering intents and what they do.

- **direction** – Integer specifying if the profile is to be used for input, output, or proof

INPUT	=	0	(or use <code>ImageCms.DIRECTION_INPUT</code>)	OUTPUT	=	1
			(or use <code>ImageCms.DIRECTION_OUTPUT</code>)	PROOF	=	2
			(or use <code>ImageCms.DIRECTION_PROOF</code>)			

Returns 1 if the intent/direction are supported, -1 if they are not.

Raises `PyCMSError` –

`PIL.ImageCms.profileToProfile(im, inputProfile, outputProfile, renderingIntent=0, outputMode=None, inPlace=False, flags=0)`

(`pyCMS`) Applies an ICC transformation to a given image, mapping from `inputProfile` to `outputProfile`.

If the input or output profiles specified are not valid filenames, a `PyCMSError` will be raised. If `inPlace` is `True` and `outputMode != im.mode`, a `PyCMSError` will be raised. If an error occurs during application of the profiles, a `PyCMSError` will be raised. If `outputMode` is not a mode supported by the `outputProfile` (or by `pyCMS`), a `PyCMSError` will be raised.

This function applies an ICC transformation to `im` from `inputProfile`'s color space to `outputProfile`'s color space using the specified rendering intent to decide how to handle out-of-gamut colors.

`OutputMode` can be used to specify that a color mode conversion is to be done using these profiles, but the specified profiles must be able to handle that mode. I.e., if converting `im` from RGB to CMYK using profiles, the input profile must handle RGB data, and the output profile must handle CMYK data.

Parameters

- **im** – An open PIL image object (i.e. `Image.new(...)` or `Image.open(...)`, etc.)
- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this image, or a profile object
- **outputProfile** – String, as a valid filename path to the ICC output profile you wish to use for this image, or a profile object
- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the transform

<code>ImageCms.INTENT_PERCEPTUAL</code>	=	0	(DEFAULT)
<code>ImageCms.INTENT_RELATIVE_COLORIMETRIC</code>	=	1	
<code>ImageCms.INTENT_SATURATION</code>	=	2	Im-
<code>ImageCms.INTENT_ABSOLUTE_COLORIMETRIC</code>	=	3	

see the `pyCMS` documentation for details on rendering intents and what they do.

- **outputMode** – A valid PIL mode for the output image (i.e. “RGB”, “CMYK”, etc.). Note: if rendering the image “inPlace”, outputMode MUST be the same mode as the input, or omitted completely. If omitted, the outputMode will be the same as the mode of the input image (im.mode)
- **inPlace** – Boolean. If True, the original image is modified in-place, and None is returned. If False (default), a new Image object is returned with the transform applied.
- **flags** – Integer (0-...) specifying additional flags

Returns Either None or a new PIL image object, depending on value of inPlace

Raises `PyCMSError` –

`PIL.ImageCms.versions()`
(pyCMS) Fetches versions.

3.4.1 CmsProfile

The ICC color profiles are wrapped in an instance of the class `CmsProfile`. The specification ICC.1:2010 contains more information about the meaning of the values in ICC profiles.

For convenience, all XYZ-values are also given as xyY-values (so they can be easily displayed in a chromaticity diagram, for example).

class `PIL.ImageCms.CmsProfile`

creation_date

Date and time this profile was first created (see 7.2.1 of ICC.1:2010).

Type `datetime.datetime` or `None`

version

The version number of the ICC standard that this profile follows (e.g. 2.0).

Type `float`

icc_version

Same as `version`, but in encoded format (see 7.2.4 of ICC.1:2010).

device_class

4-character string identifying the profile class. One of `scnr`, `mnr`, `prtr`, `link`, `spac`, `abst`, `nmcl` (see 7.2.5 of ICC.1:2010 for details).

Type `string`

xcolor_space

4-character string (padded with whitespace) identifying the color space, e.g. `XYZ_`, `RGB_` or `CMYK` (see 7.2.6 of ICC.1:2010 for details).

Note that the deprecated attribute `color_space` contains an interpreted (non-padded) variant of this (but can be empty on unknown input).

Type `string`

connection_space

4-character string (padded with whitespace) identifying the color space on the B-side of the transform (see 7.2.7 of ICC.1:2010 for details).

Note that the deprecated attribute `pcs` contains an interpreted (non-padded) variant of this (but can be empty on unknown input).

Type `string`

header_flags

The encoded header flags of the profile (see 7.2.11 of ICC.1:2010 for details).

Type `int`

header_manufacturer

4-character string (padded with whitespace) identifying the device manufacturer, which shall match the signature contained in the appropriate section of the ICC signature registry found at www.color.org (see 7.2.12 of ICC.1:2010).

Type `string`

header_model

4-character string (padded with whitespace) identifying the device model, which shall match the signature contained in the appropriate section of the ICC signature registry found at www.color.org (see 7.2.13 of ICC.1:2010).

Type `string`

attributes

Flags used to identify attributes unique to the particular device setup for which the profile is applicable (see 7.2.14 of ICC.1:2010 for details).

Type `int`

rendering_intent

The rendering intent to use when combining this profile with another profile (usually overridden at runtime, but provided here for DeviceLink and embedded source profiles, see 7.2.15 of ICC.1:2010).

One of `ImageCms.INTENT_ABSOLUTE_COLORIMETRIC`, `ImageCms.INTENT_PERCEPTUAL`, `ImageCms.INTENT_RELATIVE_COLORIMETRIC` and `ImageCms.INTENT_SATURATION`.

Type `int`

profile_id

A sequence of 16 bytes identifying the profile (via a specially constructed MD5 sum), or 16 binary zeroes if the profile ID has not been calculated (see 7.2.18 of ICC.1:2010).

Type `bytes`

copyright

The text copyright information for the profile (see 9.2.21 of ICC.1:2010).

Type `unicode` or `None`

manufacturer

The (English) display string for the device manufacturer (see 9.2.22 of ICC.1:2010).

Type `unicode` or `None`

model

The (English) display string for the device model of the device for which this profile is created (see 9.2.23 of ICC.1:2010).

Type `unicode` or `None`

profile_description

The (English) display string for the profile description (see 9.2.41 of ICC.1:2010).

Type `unicode` or `None`

target

The name of the registered characterization data set, or the measurement data for a characterization target (see 9.2.14 of ICC.1:2010).

Type unicode or None

red_colorant

The first column in the matrix used in matrix/TRC transforms (see 9.2.44 of ICC.1:2010).

Type ((X, Y, Z), (x, y, Y)) or None

green_colorant

The second column in the matrix used in matrix/TRC transforms (see 9.2.30 of ICC.1:2010).

Type ((X, Y, Z), (x, y, Y)) or None

blue_colorant

The third column in the matrix used in matrix/TRC transforms (see 9.2.4 of ICC.1:2010).

Type ((X, Y, Z), (x, y, Y)) or None

luminance

The absolute luminance of emissive devices in candelas per square metre as described by the Y channel (see 9.2.32 of ICC.1:2010).

Type ((X, Y, Z), (x, y, Y)) or None

chromaticity

The data of the phosphor/colorant chromaticity set used (red, green and blue channels, see 9.2.16 of ICC.1:2010).

Type ((x, y, Y), (x, y, Y), (x, y, Y)) or None

chromatic_adaption

The chromatic adaption matrix converts a color measured using the actual illumination conditions and relative to the actual adopted white, to an color relative to the PCS adopted white, with complete adaptation from the actual adopted white chromaticity to the PCS adopted white chromaticity (see 9.2.15 of ICC.1:2010).

Two matrices are returned, one in (X, Y, Z) space and one in (x, y, Y) space.

Type 2-tuple of 3-tuple, the first with (X, Y, Z) and the second with (x, y, Y) values

colorant_table

This tag identifies the colorants used in the profile by a unique name and set of PCSXYZ or PCSLAB values (see 9.2.19 of ICC.1:2010).

Type list of strings

colorant_table_out

This tag identifies the colorants used in the profile by a unique name and set of PCSLAB values (for DeviceLink profiles only, see 9.2.19 of ICC.1:2010).

Type list of strings

colorimetric_intent

4-character string (padded with whitespace) identifying the image state of PCS colorimetry produced using the colorimetric intent transforms (see 9.2.20 of ICC.1:2010 for details).

Type string or None

perceptual_rendering_intent_gamut

4-character string (padded with whitespace) identifying the (one) standard reference medium gamut (see 9.2.37 of ICC.1:2010 for details).

Type `string` or `None`

saturation_rendering_intent_gamut

4-character string (padded with whitespace) identifying the (one) standard reference medium gamut (see 9.2.37 of ICC.1:2010 for details).

Type `string` or `None`

technology

4-character string (padded with whitespace) identifying the device technology (see 9.2.47 of ICC.1:2010 for details).

Type `string` or `None`

media_black_point

This tag specifies the media black point and is used for generating absolute colorimetry.

This tag was available in ICC 3.2, but it is removed from version 4.

Type `((X, Y, Z), (x, y, Y))` or `None`

media_white_point_temperature

Calculates the white point temperature (see the LCMS documentation for more information).

Type `float` or `None`

viewing_condition

The (English) display string for the viewing conditions (see 9.2.48 of ICC.1:2010).

Type `unicode` or `None`

screening_description

The (English) display string for the screening conditions.

This tag was available in ICC 3.2, but it is removed from version 4.

Type `unicode` or `None`

red_primary

The XYZ-transformed of the RGB primary color red (1, 0, 0).

Type `((X, Y, Z), (x, y, Y))` or `None`

green_primary

The XYZ-transformed of the RGB primary color green (0, 1, 0).

Type `((X, Y, Z), (x, y, Y))` or `None`

blue_primary

The XYZ-transformed of the RGB primary color blue (0, 0, 1).

Type `((X, Y, Z), (x, y, Y))` or `None`

is_matrix_shaper

True if this profile is implemented as a matrix shaper (see documentation on LCMS).

Type `bool`

clut

Returns a dictionary of all supported intents and directions for the CLUT model.

The dictionary is indexed by intents (`ImageCms.INTENT_ABSOLUTE_COLORIMETRIC`, `ImageCms.INTENT_PERCEPTUAL`, `ImageCms.INTENT_RELATIVE_COLORIMETRIC` and `ImageCms.INTENT_SATURATION`).

The values are 3-tuples indexed by directions (`ImageCms.DIRECTION_INPUT`, `ImageCms.DIRECTION_OUTPUT`, `ImageCms.DIRECTION_PROOF`).

The elements of the tuple are booleans. If the value is `True`, that intent is supported for that direction.

Type dict of boolean 3-tuples

intent_supported

Returns a dictionary of all supported intents and directions.

The dictionary is indexed by intents (`ImageCms.INTENT_ABSOLUTE_COLORIMETRIC`, `ImageCms.INTENT_PERCEPTUAL`, `ImageCms.INTENT_RELATIVE_COLORIMETRIC` and `ImageCms.INTENT_SATURATION`).

The values are 3-tuples indexed by directions (`ImageCms.DIRECTION_INPUT`, `ImageCms.DIRECTION_OUTPUT`, `ImageCms.DIRECTION_PROOF`).

The elements of the tuple are booleans. If the value is `True`, that intent is supported for that direction.

Type dict of boolean 3-tuples

color_space

Deprecated but retained for backwards compatibility. Interpreted value of `xcolor_space`. May be the empty string if value could not be decoded.

Type string

pcs

Deprecated but retained for backwards compatibility. Interpreted value of `connection_space`. May be the empty string if value could not be decoded.

Type string

product_model

Deprecated but retained for backwards compatibility. ASCII-encoded value of `model`.

Type string

product_manufacturer

Deprecated but retained for backwards compatibility. ASCII-encoded value of `manufacturer`.

Type string

product_copyright

Deprecated but retained for backwards compatibility. ASCII-encoded value of `copyright`.

Type string

product_description

Deprecated but retained for backwards compatibility. ASCII-encoded value of `profile_description`.

Type string

product_desc

Deprecated but retained for backwards compatibility. ASCII-encoded value of `profile_description`.

This alias of `product_description` used to contain a derived informative string about the profile, depending on the value of the description, copyright, manufacturer and model fields).

Type string

There is one function defined on the class:

is_intent_supported (*intent*, *direction*)

Returns if the intent is supported for the given direction.

Note that you can also get this information for all intents and directions with *intent_supported*.

Parameters

- **intent** – One of `ImageCms.INTENT_ABSOLUTE_COLORIMETRIC`, `ImageCms.INTENT_PERCEPTUAL`, `ImageCms.INTENT_RELATIVE_COLORIMETRIC` and `ImageCms.INTENT_SATURATION`.
- **direction** – One of `ImageCms.DIRECTION_INPUT`, `ImageCms.DIRECTION_OUTPUT` and `ImageCms.DIRECTION_PROOF`

Returns Boolean if the intent and direction is supported.

3.5 ImageDraw Module

The `ImageDraw` module provides simple 2D graphics for *Image* objects. You can use this module to create new images, annotate or retouch existing images, and to generate graphics on the fly for web use.

For a more advanced drawing library for PIL, see the `aggdraw` module.

3.5.1 Example: Draw a gray cross over an image

```
from PIL import Image, ImageDraw

with Image.open("hopper.jpg") as im:

    draw = ImageDraw.Draw(im)
    draw.line((0, 0) + im.size, fill=128)
    draw.line((0, im.size[1], im.size[0], 0), fill=128)

    # write to stdout
    im.save(sys.stdout, "PNG")
```

3.5.2 Concepts

Coordinates

The graphics interface uses the same coordinate system as PIL itself, with (0, 0) in the upper left corner. Any pixels drawn outside of the image bounds will be discarded.

Colors

To specify colors, you can use numbers or tuples just as you would use with `PIL.Image.new()` or `PIL.Image.Image.putpixel()`. For “1”, “L”, and “I” images, use integers. For “RGB” images, use a 3-tuple containing integer values. For “F” images, use integer or floating point values.

For palette images (mode “P”), use integers as color indexes. In 1.1.4 and later, you can also use RGB 3-tuples or color names (see below). The drawing layer will automatically assign color indexes, as long as you don’t draw with more than 256 colors.

Color Names

See *Color Names* for the color names supported by Pillow.

Fonts

PIL can use bitmap fonts or OpenType/TrueType fonts.

Bitmap fonts are stored in PIL's own format, where each font typically consists of two files, one named .pil and the other usually named .pbm. The former contains font metrics, the latter raster data.

To load a bitmap font, use the load functions in the *ImageFont* module.

To load a OpenType/TrueType font, use the *truetype* function in the *ImageFont* module. Note that this function depends on third-party libraries, and may not be available in all PIL builds.

3.5.3 Example: Draw Partial Opacity Text

```
from PIL import Image, ImageDraw, ImageFont
# get an image
base = Image.open('Pillow/Tests/images/hopper.png').convert('RGBA')

# make a blank image for the text, initialized to transparent text color
txt = Image.new('RGBA', base.size, (255,255,255,0))

# get a font
fnt = ImageFont.truetype('Pillow/Tests/fonts/FreeMono.ttf', 40)
# get a drawing context
d = ImageDraw.Draw(txt)

# draw text, half opacity
d.text((10,10), "Hello", font=fnt, fill=(255,255,255,128))
# draw text, full opacity
d.text((10,60), "World", font=fnt, fill=(255,255,255,255))

out = Image.alpha_composite(base, txt)

out.show()
```

3.5.4 Functions

class PIL.ImageDraw.**Draw** (*im*, *mode=None*)

Creates an object that can be used to draw in the given image.

Note that the image will be modified in place.

Parameters

- **im** – The image to draw in.
- **mode** – Optional mode to use for color values. For RGB images, this argument can be RGB or RGBA (to blend the drawing into the image). For all other modes, this argument must be the same as the image mode. If omitted, the mode defaults to the mode of the image.

3.5.5 Methods

`PIL.ImageDraw.ImageDraw.getfont()`

Get the current default font.

Returns An image font.

`PIL.ImageDraw.ImageDraw.arc(xy, start, end, fill=None, width=0)`

Draws an arc (a portion of a circle outline) between the start and end angles, inside the given bounding box.

Parameters

- **xy** – Two points to define the bounding box. Sequence of $[(x_0, y_0), (x_1, y_1)]$ or $[x_0, y_0, x_1, y_1]$, where $x_1 \geq x_0$ and $y_1 \geq y_0$.
- **start** – Starting angle, in degrees. Angles are measured from 3 o'clock, increasing clockwise.
- **end** – Ending angle, in degrees.
- **fill** – Color to use for the arc.
- **width** – The line width, in pixels.

New in version 5.3.0.

`PIL.ImageDraw.ImageDraw.bitmap(xy, bitmap, fill=None)`

Draws a bitmap (mask) at the given position, using the current fill color for the non-zero portions. The bitmap should be a valid transparency mask (mode “1”) or matte (mode “L” or “RGBA”).

This is equivalent to doing `image.paste(xy, color, bitmap)`.

To paste pixel data into an image, use the `paste()` method on the image itself.

`PIL.ImageDraw.ImageDraw.chord(xy, start, end, fill=None, outline=None, width=1)`

Same as `arc()`, but connects the end points with a straight line.

Parameters

- **xy** – Two points to define the bounding box. Sequence of $[(x_0, y_0), (x_1, y_1)]$ or $[x_0, y_0, x_1, y_1]$, where $x_1 \geq x_0$ and $y_1 \geq y_0$.
- **outline** – Color to use for the outline.
- **fill** – Color to use for the fill.
- **width** – The line width, in pixels.

New in version 5.3.0.

`PIL.ImageDraw.ImageDraw.ellipse(xy, fill=None, outline=None, width=1)`

Draws an ellipse inside the given bounding box.

Parameters

- **xy** – Two points to define the bounding box. Sequence of either $[(x_0, y_0), (x_1, y_1)]$ or $[x_0, y_0, x_1, y_1]$, where $x_1 \geq x_0$ and $y_1 \geq y_0$.
- **outline** – Color to use for the outline.
- **fill** – Color to use for the fill.
- **width** – The line width, in pixels.

New in version 5.3.0.

`PIL.ImageDraw.ImageDraw.line(xy, fill=None, width=0, joint=None)`

Draws a line between the coordinates in the `xy` list.

Parameters

- **xy** – Sequence of either 2-tuples like `[(x, y), (x, y), ...]` or numeric values like `[x, y, x, y, ...]`.
- **fill** – Color to use for the line.
- **width** – The line width, in pixels.

New in version 1.1.5.

Note: This option was broken until version 1.1.6.

- **joint** –

Joint type between a sequence of lines. It can be “curve”, for rounded edges, or `None`.

New in version 5.3.0.

`PIL.ImageDraw.ImageDraw.pieslice(xy, start, end, fill=None, outline=None, width=1)`

Same as `arc`, but also draws straight lines between the end points and the center of the bounding box.

Parameters

- **xy** – Two points to define the bounding box. Sequence of `[(x0, y0), (x1, y1)]` or `[x0, y0, x1, y1]`, where `x1 >= x0` and `y1 >= y0`.
- **start** – Starting angle, in degrees. Angles are measured from 3 o’clock, increasing clockwise.
- **end** – Ending angle, in degrees.
- **fill** – Color to use for the fill.
- **outline** – Color to use for the outline.
- **width** – The line width, in pixels.

New in version 5.3.0.

`PIL.ImageDraw.ImageDraw.point(xy, fill=None)`

Draws points (individual pixels) at the given coordinates.

Parameters

- **xy** – Sequence of either 2-tuples like `[(x, y), (x, y), ...]` or numeric values like `[x, y, x, y, ...]`.
- **fill** – Color to use for the point.

`PIL.ImageDraw.ImageDraw.polygon(xy, fill=None, outline=None)`

Draws a polygon.

The polygon outline consists of straight lines between the given coordinates, plus a straight line between the last and the first coordinate.

Parameters

- **xy** – Sequence of either 2-tuples like `[(x, y), (x, y), ...]` or numeric values like `[x, y, x, y, ...]`.
- **outline** – Color to use for the outline.

- **fill** – Color to use for the fill.

`PIL.ImageDraw.ImageDraw.rectangle(xy, fill=None, outline=None, width=1)`

Draws a rectangle.

Parameters

- **xy** – Two points to define the bounding box. Sequence of either `[(x0, y0), (x1, y1)]` or `[x0, y0, x1, y1]`. The second point is just outside the drawn rectangle.
- **outline** – Color to use for the outline.
- **fill** – Color to use for the fill.
- **width** – The line width, in pixels.

New in version 5.3.0.

`PIL.ImageDraw.ImageDraw.shape(shape, fill=None, outline=None)`

Warning: This method is experimental.

Draw a shape.

`PIL.ImageDraw.ImageDraw.text(xy, text, fill=None, font=None, anchor=None, spacing=4, align="left", direction=None, features=None, language=None, stroke_width=0, stroke_fill=None)`

Draws the string at the given position.

Parameters

- **xy** – Top left corner of the text.
- **text** – Text to be drawn. If it contains any newline characters, the text is passed on to `multiline_text()`
- **fill** – Color to use for the text.
- **font** – An `ImageFont` instance.
- **spacing** – If the text is passed on to `multiline_text()`, the number of pixels between lines.
- **align** – If the text is passed on to `multiline_text()`, “left”, “center” or “right”.
- **direction** – Direction of the text. It can be ‘rtl’ (right to left), ‘ltr’ (left to right) or ‘ttb’ (top to bottom). Requires `libraqm`.

New in version 4.2.0.

- **features** – A list of OpenType font features to be used during text layout. This is usually used to turn on optional font features that are not enabled by default, for example ‘dlig’ or ‘ss01’, but can be also used to turn off default font features for example ‘-liga’ to disable ligatures or ‘-kern’ to disable kerning. To get all supported features, see <https://docs.microsoft.com/en-us/typography/opentype/spec/featurelist> Requires `libraqm`.

New in version 4.2.0.

- **language** – Language of the text. Different languages may use different glyph shapes or ligatures. This parameter tells the font which language the text is in, and to apply the correct substitutions as appropriate, if available. It should be a *BCP 47 language code* <<https://www.w3.org/International/articles/language-tags/>> Requires `libraqm`.

New in version 6.0.0.

- **stroke_width** – The width of the text stroke.

New in version 6.2.0.

- **stroke_fill** –

Color to use for the text stroke. If not given, will default to the `fill` parameter.

New in version 6.2.0.

`PIL.ImageDraw.ImageDraw.multiline_text(xy, text, fill=None, font=None, anchor=None, spacing=4, align="left", direction=None, features=None, language=None)`

Draws the string at the given position.

Parameters

- **xy** – Top left corner of the text.
- **text** – Text to be drawn.
- **fill** – Color to use for the text.
- **font** – An *ImageFont* instance.
- **spacing** – The number of pixels between lines.
- **align** – “left”, “center” or “right”.
- **direction** – Direction of the text. It can be ‘rtl’ (right to left), ‘ltr’ (left to right) or ‘ttb’ (top to bottom). Requires `libraqm`.

New in version 4.2.0.

- **features** – A list of OpenType font features to be used during text layout. This is usually used to turn on optional font features that are not enabled by default, for example ‘dlig’ or ‘ss01’, but can be also used to turn off default font features for example ‘-liga’ to disable ligatures or ‘-kern’ to disable kerning. To get all supported features, see <https://docs.microsoft.com/en-us/typography/opentype/spec/featurelist> Requires `libraqm`.

New in version 4.2.0.

- **language** – Language of the text. Different languages may use different glyph shapes or ligatures. This parameter tells the font which language the text is in, and to apply the correct substitutions as appropriate, if available. It should be a *BCP 47 language code* <<https://www.w3.org/International/articles/language-tags/>> Requires `libraqm`.

New in version 6.0.0.

`PIL.ImageDraw.ImageDraw.textsize(text, font=None, spacing=4, direction=None, features=None, language=None, stroke_width=0)`

Return the size of the given string, in pixels.

Parameters

- **text** – Text to be measured. If it contains any newline characters, the text is passed on to `multiline_textsize()`
- **font** – An *ImageFont* instance.
- **spacing** – If the text is passed on to `multiline_textsize()`, the number of pixels between lines.
- **direction** – Direction of the text. It can be ‘rtl’ (right to left), ‘ltr’ (left to right) or ‘ttb’ (top to bottom). Requires `libraqm`.

New in version 4.2.0.

- **features** – A list of OpenType font features to be used during text layout. This is usually used to turn on optional font features that are not enabled by default, for example ‘dlig’ or ‘ss01’, but can be also used to turn off default font features for example ‘-liga’ to disable ligatures or ‘-kern’ to disable kerning. To get all supported features, see <https://docs.microsoft.com/en-us/typography/opentype/spec/featurelist> Requires libraqm.

New in version 4.2.0.

- **language** – Language of the text. Different languages may use different glyph shapes or ligatures. This parameter tells the font which language the text is in, and to apply the correct substitutions as appropriate, if available. It should be a *BCP 47 language code* <<https://www.w3.org/International/articles/language-tags/>> Requires libraqm.

New in version 6.0.0.

- **stroke_width** – The width of the text stroke.

New in version 6.2.0.

```
PIL.ImageDraw.ImageDraw.multiline_textsize(text, font=None, spacing=4, direction=None, features=None, language=None, stroke_width=0)
```

Return the size of the given string, in pixels.

Parameters

- **text** – Text to be measured.
- **font** – An *ImageFont* instance.
- **spacing** – The number of pixels between lines.
- **direction** – Direction of the text. It can be ‘rtl’ (right to left), ‘ltr’ (left to right) or ‘ttb’ (top to bottom). Requires libraqm.

New in version 4.2.0.

- **features** – A list of OpenType font features to be used during text layout. This is usually used to turn on optional font features that are not enabled by default, for example ‘dlig’ or ‘ss01’, but can be also used to turn off default font features for example ‘-liga’ to disable ligatures or ‘-kern’ to disable kerning. To get all supported features, see <https://docs.microsoft.com/en-us/typography/opentype/spec/featurelist> Requires libraqm.

New in version 4.2.0.

- **language** – Language of the text. Different languages may use different glyph shapes or ligatures. This parameter tells the font which language the text is in, and to apply the correct substitutions as appropriate, if available. It should be a *BCP 47 language code* <<https://www.w3.org/International/articles/language-tags/>> Requires libraqm.

New in version 6.0.0.

- **stroke_width** – The width of the text stroke.

New in version 6.2.0.

```
PIL.ImageDraw.getdraw(im=None, hints=None)
```

Warning: This method is experimental.

A more advanced 2D drawing interface for PIL images, based on the WCK interface.

Parameters

- **im** – The image to draw in.
- **hints** – An optional list of hints.

Returns A (drawing context, drawing resource factory) tuple.

PIL.ImageDraw.**floodfill** (*image, xy, value, border=None, thresh=0*)

Warning: This method is experimental.

Fills a bounded region with a given color.

Parameters

- **image** – Target image.
- **xy** – Seed position (a 2-item coordinate tuple).
- **value** – Fill color.
- **border** – Optional border value. If given, the region consists of pixels with a color different from the border color. If not given, the region consists of pixels having the same color as the seed pixel.
- **thresh** – Optional threshold value which specifies a maximum tolerable difference of a pixel value from the ‘background’ in order for it to be replaced. Useful for filling regions of non- homogeneous, but similar, colors.

3.6 ImageEnhance Module

The ImageEnhance module contains a number of classes that can be used for image enhancement.

3.6.1 Example: Vary the sharpness of an image

```
from PIL import ImageEnhance

enhancer = ImageEnhance.Sharpness(image)

for i in range(8):
    factor = i / 4.0
    enhancer.enhance(factor).show("Sharpness %f" % factor)
```

Also see the `enhancer.py` demo program in the `Scripts/` directory.

3.6.2 Classes

All enhancement classes implement a common interface, containing a single method:

```
class PIL.ImageEnhance._Enhance
.. py:method:: enhance(factor)
```

Returns an enhanced image.

param factor A floating point value controlling the enhancement. Factor 1.0 always returns a copy of the original image, lower factors mean less color (brightness, contrast, etc), and higher values more. There are no restrictions on this value.

class `PIL.ImageEnhance.Color` (*image*)
Adjust image color balance.

This class can be used to adjust the colour balance of an image, in a manner similar to the controls on a colour TV set. An enhancement factor of 0.0 gives a black and white image. A factor of 1.0 gives the original image.

class `PIL.ImageEnhance.Contrast` (*image*)
Adjust image contrast.

This class can be used to control the contrast of an image, similar to the contrast control on a TV set. An enhancement factor of 0.0 gives a solid grey image. A factor of 1.0 gives the original image.

class `PIL.ImageEnhance.Brightness` (*image*)
Adjust image brightness.

This class can be used to control the brightness of an image. An enhancement factor of 0.0 gives a black image. A factor of 1.0 gives the original image.

class `PIL.ImageEnhance.Sharpness` (*image*)
Adjust image sharpness.

This class can be used to adjust the sharpness of an image. An enhancement factor of 0.0 gives a blurred image, a factor of 1.0 gives the original image, and a factor of 2.0 gives a sharpened image.

3.7 ImageFile Module

The `ImageFile` module provides support functions for the image open and save functions.

In addition, it provides a `Parser` class which can be used to decode an image piece by piece (e.g. while receiving it over a network connection). This class implements the same consumer interface as the standard `sgmlib` and `xmlib` modules.

3.7.1 Example: Parse an image

```
from PIL import ImageFile

fp = open("hopper.pgm", "rb")

p = ImageFile.Parser()

while 1:
    s = fp.read(1024)
    if not s:
        break
    p.feed(s)

im = p.close()

im.save("copy.jpg")
```

3.7.2 Parser

class `PIL.ImageFile.Parser`

Incremental image parser. This class implements the standard feed/close consumer interface.

close ()

(Consumer) Close the stream.

Returns An image object.

Raises `IOError` – If the parser failed to parse the image file either because it cannot be identified or cannot be decoded.

feed (*data*)

(Consumer) Feed data to the parser.

Parameters *data* – A string buffer.

Raises `IOError` – If the parser failed to parse the image file.

reset ()

(Consumer) Reset the parser. Note that you can only call this method immediately after you've created a parser; parser instances cannot be reused.

3.7.3 PyDecoder

class `PIL.ImageFile.PyDecoder`

Python implementation of a format decoder. Override this class and add the decoding logic in the *decode* method.

See *Writing Your Own File Decoder in Python*

cleanup ()

Override to perform decoder specific cleanup

Returns None

decode (*buffer*)

Override to perform the decoding process.

Parameters *buffer* – A bytes object with the data to be decoded.

Returns A tuple of (bytes consumed, errcode). If finished with decoding return <0 for the bytes consumed. Err codes are from *ERRORS*

init (*args*)

Override to perform decoder specific initialization

Parameters *args* – Array of args items from the tile entry

Returns None

set_as_raw (*data*, *rawmode=None*)

Convenience method to set the internal image from a stream of raw data

Parameters

- **data** – Bytes to be set
- **rawmode** – The rawmode to be used for the decoder. If not specified, it will default to the mode of the image

Returns None

setfd (*fd*)

Called from ImageFile to set the python file-like object

Parameters **fd** – A python file-like object

Returns None

setimage (*im, extents=None*)

Called from ImageFile to set the core output image for the decoder

Parameters

- **im** – A core image object
- **extents** – a 4 tuple of (x0, y0, x1, y1) defining the rectangle for this tile

Returns None

3.8 ImageFilter Module

The ImageFilter module contains definitions for a pre-defined set of filters, which can be used with the `Image.filter()` method.

3.8.1 Example: Filter an image

```
from PIL import ImageFilter

im1 = im.filter(ImageFilter.BLUR)

im2 = im.filter(ImageFilter.MinFilter(3))
im3 = im.filter(ImageFilter.MinFilter) # same as MinFilter(3)
```

3.8.2 Filters

The current version of the library provides the following set of predefined image enhancement filters:

- **BLUR**
- **CONTOUR**
- **DETAIL**
- **EDGE_ENHANCE**
- **EDGE_ENHANCE_MORE**
- **EMBOSS**
- **FIND_EDGES**
- **SHARPEN**
- **SMOOTH**
- **SMOOTH_MORE**

class `PIL.ImageFilter.Color3DLUT` (*size, table, channels=3, target_mode=None, **kwargs*)
Three-dimensional color lookup table.

Transforms 3-channel pixels using the values of the channels as coordinates in the 3D lookup table and interpolating the nearest elements.

This method allows you to apply almost any color transformation in constant time by using pre-calculated decimated tables.

New in version 5.2.0.

Parameters

- **size** – Size of the table. One int or tuple of (int, int, int). Minimal size in any dimension is 2, maximum is 65.
- **table** – Flat lookup table. A list of `channels * size**3` float elements or a list of `size**3` channels-sized tuples with floats. Channels are changed first, then first dimension, then second, then third. Value 0.0 corresponds lowest value of output, 1.0 highest.
- **channels** – Number of channels in the table. Could be 3 or 4. Default is 3.
- **target_mode** – A mode for the result image. Should have not less than `channels` channels. Default is `None`, which means that mode wouldn't be changed.

classmethod `generate` (*size, callback, channels=3, target_mode=None*)
Generates new LUT using provided callback.

Parameters

- **size** – Size of the table. Passed to the constructor.
- **callback** – Function with three parameters which correspond three color channels. Will be called `size**3` times with values from 0.0 to 1.0 and should return a tuple with `channels` elements.
- **channels** – The number of channels which should return callback.
- **target_mode** – Passed to the constructor of the resulting lookup table.

transform (*callback, with_normals=False, channels=None, target_mode=None*)
Transforms the table values using provided callback and returns a new LUT with altered values.

Parameters

- **callback** – A function which takes old lookup table values and returns a new set of values. The number of arguments which function should take is `self.channels` or `3 + self.channels` if `with_normals` flag is set. Should return a tuple of `self.channels` or `channels` elements if it is set.
- **with_normals** – If true, `callback` will be called with coordinates in the color cube as the first three arguments. Otherwise, `callback` will be called only with actual color values.
- **channels** – The number of channels in the resulting lookup table.
- **target_mode** – Passed to the constructor of the resulting lookup table.

class `PIL.ImageFilter.BoxBlur` (*radius*)

Blurs the image by setting each pixel to the average value of the pixels in a square box extending `radius` pixels in each direction. Supports float `radius` of arbitrary size. Uses an optimized implementation which runs in linear time relative to the size of the image for any `radius` value.

Parameters **radius** – Size of the box in one direction. Radius 0 does not blur, returns an identical image. Radius 1 takes 1 pixel in each direction, i.e. 9 pixels in total.

class PIL.ImageFilter.**GaussianBlur** (*radius=2*)
Gaussian blur filter.

Parameters **radius** – Blur radius.

class PIL.ImageFilter.**UnsharpMask** (*radius=2, percent=150, threshold=3*)
Unsharp mask filter.

See Wikipedia’s entry on [digital unsharp masking](#) for an explanation of the parameters.

Parameters

- **radius** – Blur Radius
- **percent** – Unsharp strength, in percent
- **threshold** – Threshold controls the minimum brightness change that will be sharpened

class PIL.ImageFilter.**Kernel** (*size, kernel, scale=None, offset=0*)
Create a convolution kernel. The current version only supports 3x3 and 5x5 integer and floating point kernels.

In the current version, kernels can only be applied to “L” and “RGB” images.

Parameters

- **size** – Kernel size, given as (width, height). In the current version, this must be (3,3) or (5,5).
- **kernel** – A sequence containing kernel weights.
- **scale** – Scale factor. If given, the result for each pixel is divided by this value. the default is the sum of the kernel weights.
- **offset** – Offset. If given, this value is added to the result, after it has been divided by the scale factor.

class PIL.ImageFilter.**RankFilter** (*size, rank*)
Create a rank filter. The rank filter sorts all pixels in a window of the given size, and returns the **rank**’th value.

Parameters

- **size** – The kernel size, in pixels.
- **rank** – What pixel value to pick. Use 0 for a min filter, $size * size / 2$ for a median filter, $size * size - 1$ for a max filter, etc.

class PIL.ImageFilter.**MedianFilter** (*size=3*)
Create a median filter. Picks the median pixel value in a window with the given size.

Parameters **size** – The kernel size, in pixels.

class PIL.ImageFilter.**MinFilter** (*size=3*)
Create a min filter. Picks the lowest pixel value in a window with the given size.

Parameters **size** – The kernel size, in pixels.

class PIL.ImageFilter.**MaxFilter** (*size=3*)
Create a max filter. Picks the largest pixel value in a window with the given size.

Parameters **size** – The kernel size, in pixels.

class PIL.ImageFilter.**ModeFilter** (*size=3*)
Create a mode filter. Picks the most frequent pixel value in a box with the given size. Pixel values that occur only once or twice are ignored; if no pixel value occurs more than twice, the original pixel value is preserved.

Parameters **size** – The kernel size, in pixels.

3.9 ImageFont Module

The ImageFont module defines a class with the same name. Instances of this class store bitmap fonts, and are used with the `PIL.ImageDraw.Draw.text()` method.

PIL uses its own font file format to store bitmap fonts. You can use the `pilfont` utility to convert BDF and PCF font descriptors (X window font formats) to this format.

Starting with version 1.1.4, PIL can be configured to support TrueType and OpenType fonts (as well as other font formats supported by the FreeType library). For earlier versions, TrueType support is only available as part of the `imToolkit` package

3.9.1 Example

```
from PIL import ImageFont, ImageDraw

draw = ImageDraw.Draw(image)

# use a bitmap font
font = ImageFont.load("arial.pil")

draw.text((10, 10), "hello", font=font)

# use a truetype font
font = ImageFont.truetype("arial.ttf", 15)

draw.text((10, 25), "world", font=font)
```

3.9.2 Functions

`PIL.ImageFont.load(filename)`

Load a font file. This function loads a font object from the given bitmap font file, and returns the corresponding font object.

Parameters `filename` – Name of font file.

Returns A font object.

Raises `IOError` – If the file could not be read.

`PIL.ImageFont.load_path(filename)`

Load font file. Same as `load()`, but searches for a bitmap font along the Python path.

Parameters `filename` – Name of font file.

Returns A font object.

Raises `IOError` – If the file could not be read.

`PIL.ImageFont.truetype(font=None, size=10, index=0, encoding="", layout_engine=None)`

Load a TrueType or OpenType font from a file or file-like object, and create a font object. This function loads a font object from the given file or file-like object, and creates a font object for a font of the given size.

Pillow uses FreeType to open font files. If you are opening many fonts simultaneously on Windows, be aware that Windows limits the number of files that can be open in C at once to 512. If you approach that limit, an `OSError` may be thrown, reporting that FreeType “cannot open resource”.

This function requires the `_imagingft` service.

Parameters

- **font** – A filename or file-like object containing a TrueType font. If the file is not found in this filename, the loader may also search in other directories, such as the `fonts/` directory on Windows or `/Library/Fonts/`, `/System/Library/Fonts/` and `~/Library/Fonts/` on macOS.
- **size** – The requested size, in points.
- **index** – Which font face to load (default is first available face).
- **encoding** – Which font encoding to use (default is Unicode). Possible encodings include (see the FreeType documentation for more information):
 - "unic" (Unicode)
 - "symb" (Microsoft Symbol)
 - "ADOB" (Adobe Standard)
 - "ADBE" (Adobe Expert)
 - "ADBC" (Adobe Custom)
 - "armn" (Apple Roman)
 - "sjis" (Shift JIS)
 - "gb " (PRC)
 - "big5"
 - "wans" (Extended Wansung)
 - "joha" (Johab)
 - "lat1" (Latin-1)

This specifies the character set to use. It does not alter the encoding of any text provided in subsequent operations.
- **layout_engine** – Which layout engine to use, if available: `ImageFont.LAYOUT_BASIC` or `ImageFont.LAYOUT_RAQM`.

Returns A font object.

Raises `IOError` – If the file could not be read.

`PIL.ImageFont.load_default()`
Load a "better than nothing" default font.

New in version 1.1.4.

Returns A font object.

3.9.3 Methods

class `PIL.ImageFont.ImageFont`
PIL font wrapper

getmask (*text*, *mode="*, **args*, ***kwargs*)
Create a bitmap for the text.

If the font uses antialiasing, the bitmap should have mode `L` and use a maximum value of 255. Otherwise, it should have mode `1`.

Parameters

- **text** – Text to render.
- **mode** – Used by some graphics drivers to indicate what mode the driver prefers; if empty, the renderer may return either mode. Note that the mode is always a string, to simplify C-level implementations.

New in version 1.1.5.

Returns An internal PIL storage memory instance as defined by the `PIL.Image.core` interface module.

getsize (*text*, **args*, ***kwargs*)

Returns width and height (in pixels) of given text.

Parameters **text** – Text to measure.

Returns (width, height)

class `PIL.ImageFont.FreeTypeFont` (*font=None*, *size=10*, *index=0*, *encoding=""*, *layout_engine=None*)

FreeType font wrapper (requires `_imagingft` service)

font_variant (*font=None*, *size=None*, *index=None*, *encoding=None*, *layout_engine=None*)

Create a copy of this FreeTypeFont object, using any specified arguments to override the settings.

Parameters are identical to the parameters used to initialize this object.

Returns A FreeTypeFont object.

get_variation_axes ()

Returns A list of the axes in a variation font.

Raises **IOError** – If the font is not a variation font.

get_variation_names ()

Returns A list of the named styles in a variation font.

Raises **IOError** – If the font is not a variation font.

getmask (*text*, *mode=""*, *direction=None*, *features=None*, *language=None*, *stroke_width=0*)

Create a bitmap for the text.

If the font uses antialiasing, the bitmap should have mode `L` and use a maximum value of 255. Otherwise, it should have mode `1`.

Parameters

- **text** – Text to render.
- **mode** – Used by some graphics drivers to indicate what mode the driver prefers; if empty, the renderer may return either mode. Note that the mode is always a string, to simplify C-level implementations.

New in version 1.1.5.

- **direction** – Direction of the text. It can be `'rtl'` (right to left), `'ltr'` (left to right) or `'tbt'` (top to bottom). Requires `libraqm`.

New in version 4.2.0.

- **features** – A list of OpenType font features to be used during text layout. This is usually used to turn on optional font features that are not enabled by default, for example `'dlig'` or `'ss01'`, but can be also used to turn off default font features for example `'liga'`

to disable ligatures or ‘-kern’ to disable kerning. To get all supported features, see <https://docs.microsoft.com/en-us/typography/opentype/spec/featurelist> Requires libraqm.

New in version 4.2.0.

- **language** – Language of the text. Different languages may use different glyph shapes or ligatures. This parameter tells the font which language the text is in, and to apply the correct substitutions as appropriate, if available. It should be a *BCP 47 language code* <<https://www.w3.org/International/articles/language-tags/>> Requires libraqm.

New in version 6.0.0.

- **stroke_width** – The width of the text stroke.

New in version 6.2.0.

Returns An internal PIL storage memory instance as defined by the `PIL.Image.core` interface module.

getmask2 (*text*, *mode*=" ", *fill*=<*built-in function fill*>, *direction*=None, *features*=None, *language*=None, *stroke_width*=0, **args*, ***kwargs*)

Create a bitmap for the text.

If the font uses antialiasing, the bitmap should have mode `L` and use a maximum value of 255. Otherwise, it should have mode `1`.

Parameters

- **text** – Text to render.
- **mode** – Used by some graphics drivers to indicate what mode the driver prefers; if empty, the renderer may return either mode. Note that the mode is always a string, to simplify C-level implementations.

New in version 1.1.5.

- **direction** – Direction of the text. It can be ‘rtl’ (right to left), ‘ltr’ (left to right) or ‘ttb’ (top to bottom). Requires libraqm.

New in version 4.2.0.

- **features** – A list of OpenType font features to be used during text layout. This is usually used to turn on optional font features that are not enabled by default, for example ‘dlig’ or ‘ss01’, but can be also used to turn off default font features for example ‘-liga’ to disable ligatures or ‘-kern’ to disable kerning. To get all supported features, see <https://docs.microsoft.com/en-us/typography/opentype/spec/featurelist> Requires libraqm.

New in version 4.2.0.

- **language** – Language of the text. Different languages may use different glyph shapes or ligatures. This parameter tells the font which language the text is in, and to apply the correct substitutions as appropriate, if available. It should be a *BCP 47 language code* <<https://www.w3.org/International/articles/language-tags/>> Requires libraqm.

New in version 6.0.0.

- **stroke_width** – The width of the text stroke.

New in version 6.2.0.

Returns A tuple of an internal PIL storage memory instance as defined by the `PIL.Image.core` interface module, and the text offset, the gap between the starting coordinate and the first marking

getmetrics ()

Returns A tuple of the font ascent (the distance from the baseline to the highest outline point) and descent (the distance from the baseline to the lowest outline point, a negative value)

getname ()

Returns A tuple of the font family (e.g. Helvetica) and the font style (e.g. Bold)

getoffset (*text*)

Returns the offset of given text. This is the gap between the starting coordinate and the first marking. Note that this gap is included in the result of *getsize* ().

Parameters *text* – Text to measure.

Returns A tuple of the x and y offset

getsize (*text*, *direction=None*, *features=None*, *language=None*, *stroke_width=0*)

Returns width and height (in pixels) of given text if rendered in font with provided direction, features, and language.

Parameters

- **text** – Text to measure.
- **direction** – Direction of the text. It can be ‘rtl’ (right to left), ‘ltr’ (left to right) or ‘ttb’ (top to bottom). Requires *libraqm*.
New in version 4.2.0.
- **features** – A list of OpenType font features to be used during text layout. This is usually used to turn on optional font features that are not enabled by default, for example ‘dlig’ or ‘ss01’, but can be also used to turn off default font features for example ‘-liga’ to disable ligatures or ‘-kern’ to disable kerning. To get all supported features, see <https://docs.microsoft.com/en-us/typography/opentype/spec/featurelist> Requires *libraqm*.
New in version 4.2.0.
- **language** – Language of the text. Different languages may use different glyph shapes or ligatures. This parameter tells the font which language the text is in, and to apply the correct substitutions as appropriate, if available. It should be a *BCP 47 language code* <<https://www.w3.org/International/articles/language-tags/>> Requires *libraqm*.
New in version 6.0.0.
- **stroke_width** – The width of the text stroke.
New in version 6.2.0.

Returns (width, height)

getsize_multiline (*text*, *direction=None*, *spacing=4*, *features=None*, *language=None*, *stroke_width=0*)

Returns width and height (in pixels) of given text if rendered in font with provided direction, features, and language, while respecting newline characters.

Parameters

- **text** – Text to measure.
- **direction** – Direction of the text. It can be ‘rtl’ (right to left), ‘ltr’ (left to right) or ‘ttb’ (top to bottom). Requires *libraqm*.
- **spacing** – The vertical gap between lines, defaulting to 4 pixels.
- **features** – A list of OpenType font features to be used during text layout. This is usually used to turn on optional font features that are not enabled by default, for example ‘dlig’ or ‘ss01’, but can be also used to turn off default font features for example ‘-liga’

to disable ligatures or ‘-kern’ to disable kerning. To get all supported features, see <https://docs.microsoft.com/en-us/typography/opentype/spec/featurelist> Requires libraqm.

- **language** – Language of the text. Different languages may use different glyph shapes or ligatures. This parameter tells the font which language the text is in, and to apply the correct substitutions as appropriate, if available. It should be a *BCP 47 language code* <<https://www.w3.org/International/articles/language-tags/>> Requires libraqm.

New in version 6.0.0.

- **stroke_width** – The width of the text stroke.

New in version 6.2.0.

Returns (width, height)

set_variation_by_axes (*axes*)

Parameters *axes* – A list of values for each axis.

Raises **IOError** – If the font is not a variation font.

set_variation_by_name (*name*)

Parameters *name* – The name of the style.

Raises **IOError** – If the font is not a variation font.

class `PIL.ImageFont.TransposedFont` (*font, orientation=None*)
 Wrapper for writing rotated or mirrored text

3.10 ImageGrab Module (macOS and Windows only)

The ImageGrab module can be used to copy the contents of the screen or the clipboard to a PIL image memory.

Note: The current version works on macOS and Windows only.

New in version 1.1.3.

`PIL.ImageGrab.grab` (*bbox=None, include_layered_windows=False, all_screens=False, xdisplay=None*)

Take a snapshot of the screen. The pixels inside the bounding box are returned as an “RGB” image on Windows or “RGBA” on macOS. If the bounding box is omitted, the entire screen is copied.

New in version 1.1.3: (Windows), 3.0.0 (macOS), 7.1.0 (Linux (X11))

Parameters

- **bbox** – What region to copy. Default is the entire screen. Note that on Windows OS, the top-left point may be negative if `all_screens=True` is used.
- **include_layered_windows** – Includes layered windows. Windows OS only.

New in version 6.1.0.

- **all_screens** – Capture all monitors. Windows OS only.

New in version 6.2.0.

- **xdisplay** –

X11 Display address. Pass **None** to grab the default system screen. Pass "" to grab the default X11 screen on Windows or macOS.

New in version 7.1.0.

Returns An image

`PIL.ImageGrab.grabclipboard()`

Take a snapshot of the clipboard image, if any.

New in version 1.1.4: (Windows), 3.3.0 (macOS)

Returns

On Windows, an image, a list of filenames, or None if the clipboard does not contain image data or filenames. Note that if a list is returned, the filenames may not represent image files.

On Mac, an image, or None if the clipboard does not contain image data.

3.11 ImageMath Module

The `ImageMath` module can be used to evaluate “image expressions”. The module provides a single `eval()` function, which takes an expression string and one or more images.

3.11.1 Example: Using the `ImageMath` module

```
from PIL import Image, ImageMath

im1 = Image.open("image1.jpg")
im2 = Image.open("image2.jpg")

out = ImageMath.eval("convert(min(a, b), 'L')", a=im1, b=im2)
out.save("result.png")
```

`PIL.ImageMath.eval(expression, environment)`

Evaluate expression in the given environment.

In the current version, `ImageMath` only supports single-layer images. To process multi-band images, use the `split()` method or `merge()` function.

Parameters

- **expression** – A string which uses the standard Python expression syntax. In addition to the standard operators, you can also use the functions described below.
- **environment** – A dictionary that maps image names to `Image` instances. You can use one or more keyword arguments instead of a dictionary, as shown in the above example. Note that the names must be valid Python identifiers.

Returns An image, an integer value, a floating point value, or a pixel tuple, depending on the expression.

3.11.2 Expression syntax

Expressions are standard Python expressions, but they’re evaluated in a non-standard environment. You can use PIL methods as usual, plus the following set of operators and functions:

Standard Operators

You can use standard arithmetical operators for addition (+), subtraction (-), multiplication (*), and division (/).

The module also supports unary minus (-), modulo (%), and power (**) operators.

Note that all operations are done with 32-bit integers or 32-bit floating point values, as necessary. For example, if you add two 8-bit images, the result will be a 32-bit integer image. If you add a floating point constant to an 8-bit image, the result will be a 32-bit floating point image.

You can force conversion using the `convert()`, `float()`, and `int()` functions described below.

Bitwise Operators

The module also provides operations that operate on individual bits. This includes and (&), or (|), and exclusive or (^). You can also invert (~) all pixel bits.

Note that the operands are converted to 32-bit signed integers before the bitwise operation is applied. This means that you'll get negative values if you invert an ordinary greyscale image. You can use the and (&) operator to mask off unwanted bits.

Bitwise operators don't work on floating point images.

Logical Operators

Logical operators like `and`, `or`, and `not` work on entire images, rather than individual pixels.

An empty image (all pixels zero) is treated as false. All other images are treated as true.

Note that `and` and `or` return the last evaluated operand, while `not` always returns a boolean value.

Built-in Functions

These functions are applied to each individual pixel.

abs (*image*)

Absolute value.

convert (*image, mode*)

Convert image to the given mode. The mode must be given as a string constant.

float (*image*)

Convert image to 32-bit floating point. This is equivalent to `convert(image, "F")`.

int (*image*)

Convert image to 32-bit integer. This is equivalent to `convert(image, "I")`.

Note that 1-bit and 8-bit images are automatically converted to 32-bit integers if necessary to get a correct result.

max (*image1, image2*)

Maximum value.

min (*image1, image2*)

Minimum value.

3.12 ImageMorph Module

The ImageMorph module provides morphology operations on images.

class PIL.ImageMorph.**LutBuilder** (*patterns=None, op_name=None*)
Bases: object

A class for building a MorphLut from a descriptive language

The input patterns is a list of a strings sequences like these:

```
4: (...  
  .1.  
 111)->1
```

(whitespaces including linebreaks are ignored). The option 4 describes a series of symmetry operations (in this case a 4-rotation), the pattern is described by:

- . or X - Ignore
- 1 - Pixel is on
- 0 - Pixel is off

The result of the operation is described after “->” string.

The default is to return the current pixel value, which is returned if no other match is found.

Operations:

- 4 - 4 way rotation
- N - Negate
- 1 - Dummy op for no other operation (an op must always be given)
- M - Mirroring

Example:

```
lb = LutBuilder(patterns = ["4:(... .1. 111)->1"])  
lut = lb.build_lut()
```

add_patterns (*patterns*)

build_default_lut ()

build_lut ()

Compile all patterns into a morphology lut.

TBD :Build based on (file) morphlut:modify_lut

get_lut ()

class PIL.ImageMorph.**MorphOp** (*lut=None, op_name=None, patterns=None*)
Bases: object

A class for binary morphological operators

apply (*image*)

Run a single morphological operation on an image

Returns a tuple of the number of changed pixels and the morphed image

get_on_pixels (*image*)

Get a list of all turned on pixels in a binary image

Returns a list of tuples of (x,y) coordinates of all matching pixels. See *Coordinate System*.

load_lut (*filename*)

Load an operator from an mrl file

match (*image*)

Get a list of coordinates matching the morphological operation on an image.

Returns a list of tuples of (x,y) coordinates of all matching pixels. See *Coordinate System*.

save_lut (*filename*)

Save an operator to an mrl file

set_lut (*lut*)

Set the lut from an external source

3.13 ImageOps Module

The ImageOps module contains a number of ‘ready-made’ image processing operations. This module is somewhat experimental, and most operators only work on L and RGB images.

New in version 1.1.3.

PIL.ImageOps.**autocontrast** (*image*, *cutoff=0*, *ignore=None*)

Maximize (normalize) image contrast. This function calculates a histogram of the input image, removes **cutoff** percent of the lightest and darkest pixels from the histogram, and remaps the image so that the darkest pixel becomes black (0), and the lightest becomes white (255).

Parameters

- **image** – The image to process.
- **cutoff** – How many percent to cut off from the histogram.
- **ignore** – The background pixel value (use None for no background).

Returns An image.

PIL.ImageOps.**colorize** (*image*, *black*, *white*, *mid=None*, *blackpoint=0*, *whitepoint=255*, *midpoint=127*)

Colorize grayscale image. This function calculates a color wedge which maps all black pixels in the source image to the first color and all white pixels to the second color. If **mid** is specified, it uses three-color mapping. The **black** and **white** arguments should be RGB tuples or color names; optionally you can use three-color mapping by also specifying **mid**. Mapping positions for any of the colors can be specified (e.g. **blackpoint**), where these parameters are the integer value corresponding to where the corresponding color should be mapped. These parameters must have logical order, such that **blackpoint** <= **midpoint** <= **whitepoint** (if **mid** is specified).

Parameters

- **image** – The image to colorize.
- **black** – The color to use for black input pixels.
- **white** – The color to use for white input pixels.
- **mid** – The color to use for midtone input pixels.
- **blackpoint** – an int value [0, 255] for the black mapping.
- **whitepoint** – an int value [0, 255] for the white mapping.

- **midpoint** – an int value [0, 255] for the midtone mapping.

Returns An image.

`PIL.ImageOps.pad(image, size, method=3, color=None, centering=(0.5, 0.5))`

Returns a sized and padded version of the image, expanded to fill the requested aspect ratio and size.

Parameters

- **image** – The image to size and crop.
- **size** – The requested output size in pixels, given as a (width, height) tuple.
- **method** – What resampling method to use. Default is `PIL.Image.BICUBIC`. See *Filters*.
- **color** – The background color of the padded image.
- **centering** – Control the position of the original image within the padded version.
(0.5, 0.5) will keep the image centered (0, 0) will keep the image aligned to the top left
(1, 1) will keep the image aligned to the bottom right

Returns An image.

`PIL.ImageOps.crop(image, border=0)`

Remove border from image. The same amount of pixels are removed from all four sides. This function works on all image modes.

See also:

`crop()`

Parameters

- **image** – The image to crop.
- **border** – The number of pixels to remove.

Returns An image.

`PIL.ImageOps.scale(image, factor, resample=3)`

Returns a rescaled image by a specific factor given in parameter. A factor greater than 1 expands the image, between 0 and 1 contracts the image.

Parameters

- **image** – The image to rescale.
- **factor** – The expansion factor, as a float.
- **resample** – What resampling method to use. Default is `PIL.Image.BICUBIC`. See *Filters*.

Returns An *Image* object.

`PIL.ImageOps.deform(image, deformer, resample=2)`

Deform the image.

Parameters

- **image** – The image to deform.
- **deformer** – A deformer object. Any object that implements a **getmesh** method can be used.

- **resample** – An optional resampling filter. Same values possible as in the `PIL.Image.transform` function.

Returns An image.

`PIL.ImageOps.equalize` (*image*, *mask=None*)

Equalize the image histogram. This function applies a non-linear mapping to the input image, in order to create a uniform distribution of grayscale values in the output image.

Parameters

- **image** – The image to equalize.
- **mask** – An optional mask. If given, only the pixels selected by the mask are included in the analysis.

Returns An image.

`PIL.ImageOps.expand` (*image*, *border=0*, *fill=0*)

Add border to the image

Parameters

- **image** – The image to expand.
- **border** – Border width, in pixels.
- **fill** – Pixel fill value (a color value). Default is 0 (black).

Returns An image.

`PIL.ImageOps.fit` (*image*, *size*, *method=3*, *bleed=0.0*, *centering=(0.5, 0.5)*)

Returns a sized and cropped version of the image, cropped to the requested aspect ratio and size.

This function was contributed by Kevin Cazabon.

Parameters

- **image** – The image to size and crop.
- **size** – The requested output size in pixels, given as a (width, height) tuple.
- **method** – What resampling method to use. Default is `PIL.Image.BICUBIC`. See *Filters*.
- **bleed** – Remove a border around the outside of the image from all four edges. The value is a decimal percentage (use 0.01 for one percent). The default value is 0 (no border). Cannot be greater than or equal to 0.5.
- **centering** – Control the cropping position. Use (0.5, 0.5) for center cropping (e.g. if cropping the width, take 50% off of the left side, and therefore 50% off the right side). (0.0, 0.0) will crop from the top left corner (i.e. if cropping the width, take all of the crop off of the right side, and if cropping the height, take all of it off the bottom). (1.0, 0.0) will crop from the bottom left corner, etc. (i.e. if cropping the width, take all of the crop off the left side, and if cropping the height take none from the top, and therefore all off the bottom).

Returns An image.

`PIL.ImageOps.flip` (*image*)

Flip the image vertically (top to bottom).

Parameters **image** – The image to flip.

Returns An image.

`PIL.ImageOps.grayscale` (*image*)

Convert the image to grayscale.

Parameters *image* – The image to convert.

Returns An image.

`PIL.ImageOps.invert` (*image*)

Invert (negate) the image.

Parameters *image* – The image to invert.

Returns An image.

`PIL.ImageOps.mirror` (*image*)

Flip image horizontally (left to right).

Parameters *image* – The image to mirror.

Returns An image.

`PIL.ImageOps.posterize` (*image, bits*)

Reduce the number of bits for each color channel.

Parameters

- **image** – The image to posterize.
- **bits** – The number of bits to keep for each channel (1-8).

Returns An image.

`PIL.ImageOps.solarize` (*image, threshold=128*)

Invert all pixel values above a threshold.

Parameters

- **image** – The image to solarize.
- **threshold** – All pixels above this greyscale level are inverted.

Returns An image.

`PIL.ImageOps.exif_transpose` (*image*)

If an image has an EXIF Orientation tag, return a new image that is transposed accordingly. Otherwise, return a copy of the image.

Parameters *image* – The image to transpose.

Returns An image.

3.14 ImagePalette Module

The `ImagePalette` module contains a class of the same name to represent the color palette of palette mapped images.

Note: This module was never well-documented. It hasn't changed since 2001, though, so it's probably safe for you to read the source code and puzzle out the internals if you need to.

The `ImagePalette` class has several methods, but they are all marked as “experimental.” Read that as you will. The `[source]` link is there for a reason.

class `PIL.ImagePalette.ImagePalette` (*mode='RGB', palette=None, size=0*)
 Color palette for palette mapped images

Parameters

- **mode** – The mode to use for the Palette. See: *Modes*. Defaults to “RGB”
- **palette** – An optional palette. If given, it must be a bytearray, an array or a list of ints between 0-255 and of length *size* times the number of colors in *mode*. The list must be aligned by channel (All R values must be contiguous in the list before G and B values.) Defaults to 0 through 255 per channel.
- **size** – An optional palette size. If given, it cannot be equal to or greater than 256. Defaults to 0.

getcolor (*color*)

Given an rgb tuple, allocate palette entry.

Warning: This method is experimental.

getdata ()

Get palette contents in format suitable for the low-level `im.putpalette` primitive.

Warning: This method is experimental.

save (*fp*)

Save palette to text file.

Warning: This method is experimental.

tobytes ()

Convert palette to bytes.

Warning: This method is experimental.

tostring ()

Convert palette to bytes.

Warning: This method is experimental.

3.15 ImagePath Module

The `ImagePath` module is used to store and manipulate 2-dimensional vector data. Path objects can be passed to the methods on the `ImageDraw` module.

class `PIL.ImagePath.Path`

A path object. The coordinate list can be any sequence object containing either 2-tuples [(*x*, *y*), ...] or numeric values [*x*, *y*, ...].

You can also create a path object from another path object.

In 1.1.6 and later, you can also pass in any object that implements Python's buffer API. The buffer should provide read access, and contain C floats in machine byte order.

The path object implements most parts of the Python sequence interface, and behaves like a list of (x, y) pairs. You can use `len()`, item access, and slicing as usual. However, the current version does not support slice assignment, or item and slice deletion.

Parameters `xy` – A sequence. The sequence can contain 2-tuples [(x, y), ...] or a flat list of numbers [x, y, ...].

PIL. `ImagePath.Path.compact` (*distance=2*)

Compacts the path, by removing points that are close to each other. This method modifies the path in place, and returns the number of points left in the path.

distance is measured as [Manhattan distance](#) and defaults to two pixels.

PIL. `ImagePath.Path.getbbox` ()

Gets the bounding box of the path.

Returns (x0, y0, x1, y1)

PIL. `ImagePath.Path.map` (*function*)

Maps the path through a function.

PIL. `ImagePath.Path.tolist` (*flat=0*)

Converts the path to a Python list [(x, y), ...].

Parameters `flat` – By default, this function returns a list of 2-tuples [(x, y), ...]. If this argument is `True`, it returns a flat list [x, y, ...] instead.

Returns A list of coordinates. See `flat`.

PIL. `ImagePath.Path.transform` (*matrix*)

Transforms the path in place, using an affine transform. The matrix is a 6-tuple (a, b, c, d, e, f), and each point is mapped as follows:

```
xOut = xIn * a + yIn * b + c
yOut = xIn * d + yIn * e + f
```

3.16 ImageQt Module

The `ImageQt` module contains support for creating PyQt5 or PySide2 `QImage` objects from PIL images.

New in version 1.1.6.

class `ImageQt.ImageQt` (*image*)

Creates an `ImageQt` object from a PIL `Image` object. This class is a subclass of `QtGui.QImage`, which means that you can pass the resulting objects directly to PyQt5/PySide2 API functions and methods.

This operation is currently supported for mode 1, L, P, RGB, and RGBA images. To handle other modes, you need to convert the image first.

3.17 ImageSequence Module

The `ImageSequence` module contains a wrapper class that lets you iterate over the frames of an image sequence.

3.17.1 Extracting frames from an animation

```

from PIL import Image, ImageSequence

with Image.open("animation.fli") as im:
    index = 1
    for frame in ImageSequence.Iterator(im):
        frame.save("frame%d.png" % index)
        index += 1

```

3.17.2 The Iterator class

class `PIL.ImageSequence.Iterator` (*im*)

This class implements an iterator object that can be used to loop over an image sequence.

You can use the `[]` operator to access elements by index. This operator will raise an `IndexError` if you try to access a nonexistent frame.

Parameters `im` – An image object.

3.18 ImageStat Module

The `ImageStat` module calculates global statistics for an image, or for a region of an image.

class `PIL.ImageStat.Stat` (*image_or_list*, *mask=None*)

Calculate statistics for the given image. If a mask is included, only the regions covered by that mask are included in the statistics. You can also pass in a previously calculated histogram.

Parameters

- **image** – A PIL image, or a precalculated histogram.
- **mask** – An optional mask.

extrema

Min/max values for each band in the image.

Note: This relies on the `histogram()` method, and simply returns the low and high bins used. This is correct for images with 8 bits per channel, but fails for other modes such as `I` or `F`. Instead, use `getextrema()` to return per-band extrema for the image. This is more correct and efficient because, for non-8-bit modes, the `histogram` method uses `getextrema()` to determine the bins used.

count

Total number of pixels for each band in the image.

sum

Sum of all pixels for each band in the image.

sum2

Squared sum of all pixels for each band in the image.

mean

Average (arithmetic mean) pixel level for each band in the image.

median

Median pixel level for each band in the image.

rms
RMS (root-mean-square) for each band in the image.

var
Variance for each band in the image.

stddev
Standard deviation for each band in the image.

3.19 ImageTk Module

The ImageTk module contains support to create and modify Tkinter BitmapImage and PhotoImage objects from PIL images.

For examples, see the demo programs in the Scripts directory.

class PIL.ImageTk.**BitmapImage** (*image=None, **kw*)

A Tkinter-compatible bitmap image. This can be used everywhere Tkinter expects an image object.

The given image must have mode “1”. Pixels having value 0 are treated as transparent. Options, if any, are passed on to Tkinter. The most commonly used option is **foreground**, which is used to specify the color for the non-transparent parts. See the Tkinter documentation for information on how to specify colours.

Parameters **image** – A PIL image.

height ()

Get the height of the image.

Returns The height, in pixels.

width ()

Get the width of the image.

Returns The width, in pixels.

class PIL.ImageTk.**PhotoImage** (*image=None, size=None, **kw*)

A Tkinter-compatible photo image. This can be used everywhere Tkinter expects an image object. If the image is an RGBA image, pixels having alpha 0 are treated as transparent.

The constructor takes either a PIL image, or a mode and a size. Alternatively, you can use the **file** or **data** options to initialize the photo image object.

Parameters

- **image** – Either a PIL image, or a mode string. If a mode string is used, a size must also be given.
- **size** – If the first argument is a mode string, this defines the size of the image.
- **file** – A filename to load the image from (using `Image.open(file)`).
- **data** – An 8-bit string containing image data (as loaded from an image file).

height ()

Get the height of the image.

Returns The height, in pixels.

paste (*im, box=None*)

Paste a PIL image into the photo image. Note that this can be very slow if the photo image is displayed.

Parameters

- **im** – A PIL image. The size must match the target region. If the mode does not match, the image is converted to the mode of the bitmap image.
- **box** – A 4-tuple defining the left, upper, right, and lower pixel coordinate. See *Coordinate System*. If None is given instead of a tuple, all of the image is assumed.

width()

Get the width of the image.

Returns The width, in pixels.

3.20 ImageWin Module (Windows-only)

The ImageWin module contains support to create and display images on Windows.

ImageWin can be used with PythonWin and other user interface toolkits that provide access to Windows device contexts or window handles. For example, Tkinter makes the window handle available via the `winfo_id` method:

```
from PIL import ImageWin

dib = ImageWin.Dib(...)

hwnd = ImageWin.HWND(widget.winfo_id())
dib.draw(hwnd, xy)
```

class PIL.ImageWin.Dib (*image, size=None*)

A Windows bitmap with the given mode and size. The mode can be one of “1”, “L”, “P”, or “RGB”.

If the display requires a palette, this constructor creates a suitable palette and associates it with the image. For an “L” image, 128 greylevels are allocated. For an “RGB” image, a 6x6x6 colour cube is used, together with 20 greylevels.

To make sure that palettes work properly under Windows, you must call the **palette** method upon certain events from Windows.

Parameters

- **image** – Either a PIL image, or a mode string. If a mode string is used, a size must also be given. The mode can be one of “1”, “L”, “P”, or “RGB”.
- **size** – If the first argument is a mode string, this defines the size of the image.

draw (*handle, dst, src=None*)

Same as `expose`, but allows you to specify where to draw the image, and what part of it to draw.

The destination and source areas are given as 4-tuple rectangles. If the source is omitted, the entire image is copied. If the source and the destination have different sizes, the image is resized as necessary.

expose (*handle*)

Copy the bitmap contents to a device context.

Parameters **handle** – Device context (HDC), cast to a Python integer, or an HDC or HWND instance. In PythonWin, you can use the `CDC.GetHandleAttrib()` to get a suitable handle.

frombytes (*buffer*)

Load display memory contents from byte data.

Parameters **buffer** – A buffer containing display data (usually data returned from `tobytes`)

paste (*im*, *box=None*)

Paste a PIL image into the bitmap image.

Parameters

- **im** – A PIL image. The size must match the target region. If the mode does not match, the image is converted to the mode of the bitmap image.
- **box** – A 4-tuple defining the left, upper, right, and lower pixel coordinate. See *Coordinate System*. If None is given instead of a tuple, all of the image is assumed.

query_palette (*handle*)

Installs the palette associated with the image in the given device context.

This method should be called upon **QUERYNEWPALETTE** and **PALETTECHANGED** events from Windows. If this method returns a non-zero value, one or more display palette entries were changed, and the image should be redrawn.

Parameters **handle** – Device context (HDC), cast to a Python integer, or an HDC or HWND instance.

Returns A true value if one or more entries were changed (this indicates that the image should be redrawn).

tobytes ()

Copy display memory contents to bytes object.

Returns A bytes object containing display data.

class PIL.ImageWin.**HDC** (*dc*)

Wraps an HDC integer. The resulting object can be passed to the *draw()* and *expose()* methods.

class PIL.ImageWin.**HWND** (*wnd*)

Wraps an HWND integer. The resulting object can be passed to the *draw()* and *expose()* methods, instead of a DC.

3.21 ExifTags Module

The `ExifTags` module exposes two dictionaries which provide constants and clear-text names for various well-known EXIF tags.

class PIL.ExifTags.**TAGS**

The TAG dictionary maps 16-bit integer EXIF tag enumerations to descriptive string names. For instance:

```
>>> from PIL.ExifTags import TAGS
>>> TAGS[0x010e]
'ImageDescription'
```

class PIL.ExifTags.**GPSTAGS**

The GPSTAGS dictionary maps 8-bit integer EXIF gps enumerations to descriptive string names. For instance:

```
>>> from PIL.ExifTags import GPSTAGS
>>> GPSTAGS[20]
'GPSDestLatitude'
```

3.22 TiffTags Module

The `TiffTags` module exposes many of the standard TIFF metadata tag numbers, names, and type information.

`PIL.TiffTags.lookup(tag)`

Parameters `tag` – Integer tag number

Returns Taginfo namedtuple, From the `TAGS_V2` info if possible, otherwise just populating the value and name from `TAGS`. If the tag is not recognized, “unknown” is returned for the name

New in version 3.1.0.

class `PIL.TiffTags.TagInfo`

```
__init__(self, value=None, name="unknown", type=None, length=0, enum=None)
```

Parameters

- **value** – Integer Tag Number
- **name** – Tag Name
- **type** – Integer type from `PIL.TiffTags.TYPES`
- **length** – Array length: 0 == variable, 1 == single value, n = fixed
- **enum** – Dict of name:integer value options for an enumeration

```
cvt_enum(self, value)
```

Parameters `value` – The enumerated value name

Returns The integer corresponding to the name.

New in version 3.0.0.

`PIL.TiffTags.TAGS_V2`

The `TAGS_V2` dictionary maps 16-bit integer tag numbers to `PIL.TagTypes.TagInfo` tuples for metadata fields defined in the TIFF spec.

New in version 3.0.0.

`PIL.TiffTags.TAGS`

The `TAGS` dictionary maps 16-bit integer TIFF tag number to descriptive string names. For instance:

```
>>> from PIL.TiffTags import TAGS
>>> TAGS[0x010e]
'ImageDescription'
```

This dictionary contains a superset of the tags in `TAGS_V2`, common EXIF tags, and other well known metadata tags.

`PIL.TiffTags.TYPES`

The `TYPES` dictionary maps the TIFF type short integer to a human readable type name.

3.23 PSDraw Module

The `PSDraw` module provides simple print support for Postscript printers. You can print text, graphics and images through this module.

class `PIL.PSDraw.PSDraw` (*fp=None*)

Sets up printing to the given file. If **fp** is omitted, `sys.stdout` is assumed.

begin_document (*id=None*)

Set up printing of a document. (Write Postscript DSC header.)

end_document ()

Ends printing. (Write Postscript DSC footer.)

image (*box, im, dpi=None*)

Draw a PIL image, centered in the given box.

line (*xy0, xy1*)

Draws a line between the two points. Coordinates are given in Postscript point coordinates (72 points per inch, (0, 0) is the lower left corner of the page).

rectangle (*box*)

Draws a rectangle.

Parameters **box** – A 4-tuple of integers whose order and function is currently undocumented.

Hint: the tuple is passed into this format string:

```
%d %d M %d %d 0 Vr
```

setfont (*font, size*)

Selects which font to use.

Parameters

- **font** – A Postscript font name
- **size** – Size in points.

text (*xy, text*)

Draws text at the given position. You must use `setfont()` before calling this method.

3.24 PixelAccess Class

The `PixelAccess` class provides read and write access to `PIL.Image` data at a pixel level.

Note: Accessing individual pixels is fairly slow. If you are looping over all of the pixels in an image, there is likely a faster way using other parts of the Pillow API.

3.24.1 Example

The following script loads an image, accesses one pixel from it, then changes it.

```
from PIL import Image
with Image.open('hopper.jpg') as im:
    px = im.load()
    print(px[4,4])
    px[4,4] = (0,0,0)
    print(px[4,4])
```

Results in the following:


```
(23, 24, 68)
(0, 0, 0)
```

Access using negative indexes is also possible.

```
px[-1,-1] = (0,0,0)
print (px[-1,-1])
```

3.24.2 PixelAccess Class

class PixelAccess

__setitem__(self, xy, color):

Modifies the pixel at x,y. The color is given as a single numerical value for single band images, and a tuple for multi-band images

Parameters

- **xy** – The pixel coordinate, given as (x, y).
- **color** – The pixel value according to its mode. e.g. tuple (r, g, b) for RGB mode)

__getitem__(self, xy):

Returns the pixel at x,y. The pixel is returned as a single value for single band images or a tuple for multiple band images

param xy The pixel coordinate, given as (x, y).

returns a pixel value for single band images, a tuple of pixel values for multiband images.

putpixel(self, xy, color):

Modifies the pixel at x,y. The color is given as a single numerical value for single band images, and a tuple for multi-band images. In addition to this, RGB and RGBA tuples are accepted for P images.

Parameters

- **xy** – The pixel coordinate, given as (x, y).
- **color** – The pixel value according to its mode. e.g. tuple (r, g, b) for RGB mode)

getpixel(self, xy):

Returns the pixel at x,y. The pixel is returned as a single value for single band images or a tuple for multiple band images

param xy The pixel coordinate, given as (x, y).

returns a pixel value for single band images, a tuple of pixel values for multiband images.

3.25 PyAccess Module

The `PyAccess` module provides a CFFI/Python implementation of the *PixelAccess Class*. This implementation is far faster on PyPy than the `PixelAccess` version.

Note: Accessing individual pixels is fairly slow. If you are looping over all of the pixels in an image, there is likely a faster way using other parts of the Pillow API.

3.25.1 Example

The following script loads an image, accesses one pixel from it, then changes it.

```
from PIL import Image
with Image.open('hopper.jpg') as im:
    px = im.load()
print (px[4,4])
px[4,4] = (0,0,0)
print (px[4,4])
```

Results in the following:

```
(23, 24, 68)
(0, 0, 0)
```

Access using negative indexes is also possible.

```
px[-1,-1] = (0,0,0)
print (px[-1,-1])
```

3.25.2 PyAccess Class

3.26 PIL Package (autodoc of remaining modules)

Reference for modules whose documentation has not yet been ported or written can be found here.

3.26.1 BdfFontFile Module

```
class PIL.BdfFontFile.BdfFontFile(fp)
    Bases: PIL.FontFile.FontFile
PIL.BdfFontFile.bdf_char(f)
```

3.26.2 ContainerIO Module

```
class PIL.ContainerIO.ContainerIO(file, offset, length)
    Bases: object
    isatty()
    read(n=0)
        Read data.
```

Parameters *n* – Number of bytes to read. If omitted or zero, read until end of region.

Returns An 8-bit string.

readline()

Read a line of text.

Returns An 8-bit string.**readlines()**

Read multiple lines of text.

Returns A list of 8-bit strings.**seek(*offset*, *mode*=0)**

Move file pointer.

Parameters

- **offset** – Offset in bytes.
- **mode** – Starting position. Use 0 for beginning of region, 1 for current offset, and 2 for end of region. You cannot move the pointer outside the defined region.

tell()

Get current file pointer.

Returns Offset from start of region, in bytes.

3.26.3 FontFile Module

class PIL.FontFile.**FontFile**

Bases: object

bitmap = None**compile()**

Create metrics and bitmap

save(*filename*)

Save font

PIL.FontFile.**putil6(*fp*, *values*)**

3.26.4 GdImageFile Module

class PIL.GdImageFile.**GdImageFile** (*fp*=None, *filename*=None)Bases: PIL.ImageFile.**ImageFile****format** = 'GD'**format_description** = 'GD uncompressed images'PIL.GdImageFile.**open(*fp*, *mode*='r')**

Load texture from a GD image file.

Parameters

- **filename** – GD file name, or an opened file handle.
- **mode** – Optional mode. In this version, if the mode argument is given, it must be “r”.

Returns An image instance.**Raises** **IOError** – If the image could not be read.

3.26.5 GimpGradientFile Module

class PIL.GimpGradientFile.**GimpGradientFile** (*fp*)
Bases: *PIL.GimpGradientFile.GradientFile*

class PIL.GimpGradientFile.**GradientFile**
Bases: object

getpalette (*entries=256*)

gradient = None

PIL.GimpGradientFile.**curved** (*middle, pos*)

PIL.GimpGradientFile.**linear** (*middle, pos*)

PIL.GimpGradientFile.**sine** (*middle, pos*)

PIL.GimpGradientFile.**sphere_decreasing** (*middle, pos*)

PIL.GimpGradientFile.**sphere_increasing** (*middle, pos*)

3.26.6 GimpPaletteFile Module

class PIL.GimpPaletteFile.**GimpPaletteFile** (*fp*)
Bases: object

getpalette ()

rawmode = 'RGB'

3.26.7 ImageDraw2 Module

class PIL.ImageDraw2.**Brush** (*color, opacity=255*)
Bases: object

class PIL.ImageDraw2.**Draw** (*image, size=None, color=None*)
Bases: object

arc (*xy, start, end, *options*)

chord (*xy, start, end, *options*)

ellipse (*xy, *options*)

flush ()

line (*xy, *options*)

pieslice (*xy, start, end, *options*)

polygon (*xy, *options*)

rectangle (*xy, *options*)

render (*op, xy, pen, brush=None*)

settransform (*offset*)

text (*xy, text, font*)

textsize (*text, font*)

```
class PIL.ImageDraw2.Font (color, file, size=12)
    Bases: object
```

```
class PIL.ImageDraw2.Pen (color, width=1, opacity=255)
    Bases: object
```

3.26.8 ImageShow Module

```
class PIL.ImageShow.DisplayViewer
    Bases: PIL.ImageShow.UnixViewer

    get_command_ex (file, **options)
```

```
class PIL.ImageShow.EogViewer
    Bases: PIL.ImageShow.UnixViewer

    get_command_ex (file, **options)
```

```
class PIL.ImageShow.UnixViewer
    Bases: PIL.ImageShow.Viewer

    format = 'PNG'

    get_command (file, **options)

    options = {'compress_level': 1}

    show_file (file, **options)
        Display given file
```

```
class PIL.ImageShow.Viewer
    Bases: object

    Base class for viewers.

    format = None

    get_command (file, **options)

    get_format (image)
        Return format name, or None to save as PGM/PPM

    options = {}

    save_image (image)
        Save to temporary file, and return filename

    show (image, **options)

    show_file (file, **options)
        Display given file

    show_image (image, **options)
        Display given image
```

```
class PIL.ImageShow.XVViewer
    Bases: PIL.ImageShow.UnixViewer

    get_command_ex (file, title=None, **options)
```

```
PIL.ImageShow.register (viewer, order=1)
```

```
PIL.ImageShow.show (image, title=None, **options)
    Display a given image.
```

Parameters

- **image** – An image object.
- **title** – Optional title. Not all viewers can display the title.
- ****options** – Additional viewer options.

Returns True if a suitable viewer was found, false otherwise.

3.26.9 ImageTransform Module

class PIL.ImageTransform.**AffineTransform**(*data*)

Bases: *PIL.ImageTransform.Transform*

Define an affine image transform.

This function takes a 6-tuple (a, b, c, d, e, f) which contain the first two rows from an affine transform matrix. For each pixel (x, y) in the output image, the new value is taken from a position (a x + b y + c, d x + e y + f) in the input image, rounded to nearest pixel.

This function can be used to scale, translate, rotate, and shear the original image.

See *transform()*

Parameters matrix – A 6-tuple (a, b, c, d, e, f) containing the first two rows from an affine transform matrix.

method = 0

class PIL.ImageTransform.**ExtentTransform**(*data*)

Bases: *PIL.ImageTransform.Transform*

Define a transform to extract a subregion from an image.

Maps a rectangle (defined by two corners) from the image to a rectangle of the given size. The resulting image will contain data sampled from between the corners, such that (x0, y0) in the input image will end up at (0,0) in the output image, and (x1, y1) at size.

This method can be used to crop, stretch, shrink, or mirror an arbitrary rectangle in the current image. It is slightly slower than crop, but about as fast as a corresponding resize operation.

See *transform()*

Parameters bbox – A 4-tuple (x0, y0, x1, y1) which specifies two points in the input image's coordinate system. See *Coordinate System*.

method = 1

class PIL.ImageTransform.**MeshTransform**(*data*)

Bases: *PIL.ImageTransform.Transform*

Define a mesh image transform. A mesh transform consists of one or more individual quad transforms.

See *transform()*

Parameters data – A list of (bbox, quad) tuples.

method = 4

class PIL.ImageTransform.**QuadTransform**(*data*)

Bases: *PIL.ImageTransform.Transform*

Define a quad image transform.

Maps a quadrilateral (a region defined by four corners) from the image to a rectangle of the given size.

See `transform()`

Parameters `xy` – An 8-tuple (x0, y0, x1, y1, x2, y2, x3, y3) which contain the upper left, lower left, lower right, and upper right corner of the source quadrilateral.

method = 3

```
class PIL.ImageTransform.Transform(data)
    Bases: PIL.Image.ImageTransformHandler

    getdata()

    transform(size, image, **options)
```

3.26.10 JpegPresets Module

JPEG quality settings equivalent to the Photoshop settings.

More presets can be added to the presets dict if needed.

Can be use when saving JPEG file.

To apply the preset, specify:

```
quality="preset_name"
```

To apply only the quantization table:

```
qtables="preset_name"
```

To apply only the subsampling setting:

```
subsampling="preset_name"
```

Example:

```
im.save("image_name.jpg", quality="web_high")
```

Subsampling

Subsampling is the practice of encoding images by implementing less resolution for chroma information than for luma information. (ref.: https://en.wikipedia.org/wiki/Chroma_subsampling)

Possible subsampling values are 0, 1 and 2 that correspond to 4:4:4, 4:2:2 and 4:2:0.

You can get the subsampling of a JPEG with the `JpegImagePlugin.get_sampling(im)` function.

In JPEG compressed data a JPEG marker is used instead of an EXIF tag. (ref.: <https://www.exiv2.org/tags.html>)

Quantization tables

They are values use by the DCT (Discrete cosine transform) to remove *unnecessary* information from the image (the lossy part of the compression). (ref.: https://en.wikipedia.org/wiki/Quantization_matrix#Quantization_matrices, <https://en.wikipedia.org/wiki/JPEG#Quantization>)

You can get the quantization tables of a JPEG with:

```
im.quantization
```

This will return a dict with a number of arrays. You can pass this dict directly as the `qtables` argument when saving a JPEG.

The tables format between `im.quantization` and `quantization` in presets differ in 3 ways:

1. The base container of the preset is a list with sublists instead of dict. `dict[0] -> list[0]`, `dict[1] -> list[1]`, ...
2. Each table in a preset is a list instead of an array.
3. The zigzag order is remove in the preset (needed by libjpeg >= 6a).

You can convert the dict format to the preset format with the `JpegImagePlugin.convert_dict_qtables(dict_qtables)` function.

Libjpeg ref.: <https://web.archive.org/web/20120328125543/http://www.jpegcameras.com/libjpeg/libjpeg-3.html>

3.26.11 PaletteFile Module

```
class PIL.PaletteFile.PaletteFile(fp)
    Bases: object
    getpalette()
    rawmode = 'RGB'
```

3.26.12 PcfFontFile Module

```
class PIL.PcfFontFile.PcfFontFile(fp, charset_encoding='iso8859-1')
    Bases: PIL.FontFile.FontFile
    name = 'name'
PIL.PcfFontFile.sz(s, o)
```

3.26.13 PngImagePlugin.iTXt Class

```
class PIL.PngImagePlugin.iTXt
    Bases: str
    Subclass of string to allow iTXt chunks to look like strings while keeping their extra information
    __new__(cls, text, lang, tkey)
    Parameters
        • value – value for this key
        • lang – language code
        • tkey – UTF-8 version of the key name
```

3.26.14 PngImagePlugin.PngInfo Class

```
class PIL.PngImagePlugin.PngInfo
    Bases: object
    PNG chunk container (for use with save(pnginfo=))
```


add (*cid, data*)

Appends an arbitrary chunk. Use with caution.

Parameters

- **cid** – a byte string, 4 bytes long.
- **data** – a byte string of the encoded data

add_itxt (*key, value, lang="", tkey="", zip=False*)

Appends an iTXt chunk.

Parameters

- **key** – latin-1 encodable text key name
- **value** – value for this key
- **lang** – language code
- **tkey** – UTF-8 version of the key name
- **zip** – compression flag

add_text (*key, value, zip=False*)

Appends a text chunk.

Parameters

- **key** – latin-1 encodable text key name
- **value** – value for this key, text or an *PIL.PngImagePlugin.iTXt* instance
- **zip** – compression flag

3.26.15 TarIO Module

class *PIL.TarIO.TarIO* (*tarfile, file*)

Bases: *PIL.ContainerIO.ContainerIO*

close ()

3.26.16 WalImageFile Module

PIL.WalImageFile.open (*filename*)

Load texture from a Quake2 WAL texture file.

By default, a Quake2 standard palette is attached to the texture. To override the palette, use the `putpalette` method.

Parameters **filename** – WAL file name, or an opened file handle.

Returns An image instance.

3.26.17 _binary Module

PIL._binary.i16be (*c, o=0*)

PIL._binary.i16le (*c, o=0*)

Converts a 2-bytes (16 bits) string to an unsigned integer.

Parameters

- **c** – string containing bytes to convert
- **o** – offset of bytes to convert in string

`PIL._binary.i32be(c, o=0)`

`PIL._binary.i32le(c, o=0)`

Converts a 4-bytes (32 bits) string to an unsigned integer.

Parameters

- **c** – string containing bytes to convert
- **o** – offset of bytes to convert in string

`PIL._binary.i8(c)`

`PIL._binary.o16be(i)`

`PIL._binary.o16le(i)`

`PIL._binary.o32be(i)`

`PIL._binary.o32le(i)`

`PIL._binary.o8(i)`

`PIL._binary.si16le(c, o=0)`

Converts a 2-bytes (16 bits) string to a signed integer.

Parameters

- **c** – string containing bytes to convert
- **o** – offset of bytes to convert in string

`PIL._binary.si32le(c, o=0)`

Converts a 4-bytes (32 bits) string to a signed integer.

Parameters

- **c** – string containing bytes to convert
- **o** – offset of bytes to convert in string

3.27 Plugin reference

3.27.1 BmpImagePlugin Module

class `PIL.BmpImagePlugin.BmpImageFile` (*fp=None, filename=None*)

Bases: `PIL.ImageFile.ImageFile`

Image plugin for the Windows Bitmap format (BMP)

BITFIELDS = 3

COMPRESSIONS = {'BITFIELDS': 3, 'JPEG': 4, 'PNG': 5, 'RAW': 0, 'RLE4': 2, 'RLE8': 1}

JPEG = 4

PNG = 5

RAW = 0

RLE4 = 2

```

RLE8 = 1
format = 'BMP'
format_description = 'Windows Bitmap'
k = 'PNG'
v = 5
class PIL.BmpImagePlugin.DibImageFile (fp=None, filename=None)
    Bases: PIL.BmpImagePlugin.BmpImageFile
    format = 'DIB'
    format_description = 'Windows Bitmap'

```

3.27.2 BufrStubImagePlugin Module

```

class PIL.BufrStubImagePlugin.BufrStubImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.StubImageFile
    format = 'BUFR'
    format_description = 'BUFR'

```

`PIL.BufrStubImagePlugin.register_handler(handler)`
 Install application-specific BUFR image handler.

Parameters `handler` – Handler object.

3.27.3 CurImagePlugin Module

```

class PIL.CurImagePlugin.CurImageFile (fp=None, filename=None)
    Bases: PIL.BmpImagePlugin.BmpImageFile
    format = 'CUR'
    format_description = 'Windows Cursor'

```

3.27.4 DcxImagePlugin Module

```

class PIL.DcxImagePlugin.DcxImageFile (fp=None, filename=None)
    Bases: PIL.PcxImagePlugin.PcxImageFile
    format = 'DCX'
    format_description = 'Intel DCX'
    is_animated
    n_frames
    seek (frame)

```

Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method raises an **EOFError** exception. When a sequence file is opened, the library automatically seeks to frame 0.

See `tell()`.

Parameters `frame` – Frame number, starting at 0.

Raises EOFError – If the call attempts to seek beyond the end of the sequence.

tell()

Returns the current frame number. See *seek()*.

Returns Frame number, starting with 0.

3.27.5 EpsImagePlugin Module

class PIL.EpsImagePlugin.**EpsImageFile** (*fp=None, filename=None*)

Bases: PIL.ImageFile.ImageFile

EPS File Parser for the Python Imaging Library

format = 'EPS'

format_description = 'Encapsulated Postscript'

load (*scale=1*)

Load image data based on tile list

load_seek (**args, **kwargs*)

mode_map = {1: 'L', 2: 'LAB', 3: 'RGB', 4: 'CMYK'}

PIL.EpsImagePlugin.**Ghostscript** (*tile, size, fp, scale=1*)

Render an image using Ghostscript

class PIL.EpsImagePlugin.**PSFile** (*fp*)

Bases: object

Wrapper for bytesio object that treats either CR or LF as end of line.

readline ()

seek (*offset, whence=0*)

PIL.EpsImagePlugin.**has_ghostscript** ()

3.27.6 FitsStubImagePlugin Module

class PIL.FitsStubImagePlugin.**FITSStubImageFile** (*fp=None, filename=None*)

Bases: PIL.ImageFile.StubImageFile

format = 'FITS'

format_description = 'FITS'

PIL.FitsStubImagePlugin.**register_handler** (*handler*)

Install application-specific FITS image handler.

Parameters *handler* – Handler object.

3.27.7 FliImagePlugin Module

class PIL.FliImagePlugin.**FliImageFile** (*fp=None, filename=None*)

Bases: PIL.ImageFile.ImageFile

format = 'FLI'

format_description = 'Autodesk FLI/FLC Animation'

is_animated

n_frames

seek (*frame*)

Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method raises an **EOFError** exception. When a sequence file is opened, the library automatically seeks to frame 0.

See *tell()*.

Parameters **frame** – Frame number, starting at 0.

Raises **EOFError** – If the call attempts to seek beyond the end of the sequence.

tell ()

Returns the current frame number. See *seek()*.

Returns Frame number, starting with 0.

3.27.8 FpxImagePlugin Module

class PIL.FpxImagePlugin.**FpxImageFile** (*fp=None, filename=None*)

Bases: PIL.ImageFile.ImageFile

format = 'FPX'

format_description = 'FlashPix'

load ()

Load image data based on tile list

3.27.9 GbrImagePlugin Module

class PIL.GbrImagePlugin.**GbrImageFile** (*fp=None, filename=None*)

Bases: PIL.ImageFile.ImageFile

format = 'GBR'

format_description = 'GIMP brush file'

load ()

Load image data based on tile list

3.27.10 GifImagePlugin Module

class PIL.GifImagePlugin.**GifImageFile** (*fp=None, filename=None*)

Bases: PIL.ImageFile.ImageFile

data ()

format = 'GIF'

format_description = 'CompuServe GIF'

global_palette = None

is_animated

load_end ()

n_frames

seek (*frame*)

Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method raises an **EOFError** exception. When a sequence file is opened, the library automatically seeks to frame 0.

See *tell()*.

Parameters *frame* – Frame number, starting at 0.

Raises **EOFError** – If the call attempts to seek beyond the end of the sequence.

tell ()

Returns the current frame number. See *seek()*.

Returns Frame number, starting with 0.

`PIL.GifImagePlugin.get_interlace(im)`

`PIL.GifImagePlugin.getdata(im, offset=(0, 0), **params)`

Legacy Method

Return a list of strings representing this image. The first string is a local image header, the rest contains encoded image data.

Parameters

- **im** – Image object
- **offset** – Tuple of (x, y) pixels. Defaults to (0,0)
- ****params** – E.g. duration or other encoder info parameters

Returns List of Bytes containing gif encoded frame data

`PIL.GifImagePlugin.getheader(im, palette=None, info=None)`

Legacy Method to get Gif data from image.

Warning:: May modify image data.

Parameters

- **im** – Image object
- **palette** – bytes object containing the source palette, or ...
- **info** – encoderinfo

Returns tuple of(list of header items, optimized palette)

3.27.11 GribStubImagePlugin Module

class `PIL.GribStubImagePlugin.GribStubImageFile` (*fp=None, filename=None*)

Bases: `PIL.ImageFile.StubImageFile`

format = 'GRIB'

format_description = 'GRIB'

`PIL.GribStubImagePlugin.register_handler(handler)`

Install application-specific GRIB image handler.

Parameters *handler* – Handler object.

3.27.12 Hdf5StubImagePlugin Module

class PIL.Hdf5StubImagePlugin.HDF5StubImageFile (*fp=None, filename=None*)
 Bases: PIL.ImageFile.StubImageFile

format = 'HDF5'

format_description = 'HDF5'

PIL.Hdf5StubImagePlugin.**register_handler** (*handler*)
 Install application-specific HDF5 image handler.

Parameters *handler* – Handler object.

3.27.13 IcnsImagePlugin Module

class PIL.IcnsImagePlugin.IcnsFile (*fobj*)
 Bases: object

SIZES = {(16, 16, 1): [(b'icp4', <function read_png_or_jpeg2000>), (b'is32', <function

bestsize ()

datafor*size* ()

Get an icon resource as {channel: array}. Note that the arrays are bottom-up like windows bitmaps and will likely need to be flipped or transposed in some way.

getimage (*size=None*)

itersizes ()

class PIL.IcnsImagePlugin.IcnsImageFile (*fp=None, filename=None*)
 Bases: PIL.ImageFile.ImageFile

PIL image support for Mac OS .icns files. Chooses the best resolution, but will possibly load a different size image if you mutate the size attribute before calling 'load'.

The info dictionary has a key 'sizes' that is a list of sizes that the icns file has.

format = 'ICNS'

format_description = 'Mac OS icns resource'

load ()

Load image data based on tile list

size

PIL.IcnsImagePlugin.**nextheader** (*fobj*)

PIL.IcnsImagePlugin.**read_32** (*fobj, start_length, size*)

Read a 32bit RGB icon resource. Seems to be either uncompressed or an RLE packbits-like scheme.

PIL.IcnsImagePlugin.**read_32t** (*fobj, start_length, size*)

PIL.IcnsImagePlugin.**read_mk** (*fobj, start_length, size*)

PIL.IcnsImagePlugin.**read_png_or_jpeg2000** (*fobj, start_length, size*)

3.27.14 IcoImagePlugin Module

class PIL.IcoImagePlugin.IcoFile (*buf*)

Bases: object

frame (*idx*)

Get an image from frame *idx*

getentryindex (*size, bpp=False*)

getimage (*size, bpp=False*)

Get an image from the icon

sizes ()

Get a list of all available icon sizes and color depths.

class PIL.IcoImagePlugin.IcoImageFile (*fp=None, filename=None*)

Bases: PIL.ImageFile.ImageFile

PIL read-only image support for Microsoft Windows .ico files.

By default the largest resolution image in the file will be loaded. This can be changed by altering the 'size' attribute before calling 'load'.

The info dictionary has a key 'sizes' that is a list of the sizes available in the icon file.

Handles classic, XP and Vista icon formats.

When saving, PNG compression is used. Support for this was only added in Windows Vista.

This plugin is a refactored version of Win32IconImagePlugin by Bryan Davis <casadebender@gmail.com>. <https://code.google.com/archive/p/casadebender/wikis/Win32IconImagePlugin.wiki>

format = 'ICO'

format_description = 'Windows Icon'

load ()

Load image data based on tile list

load_seek ()

size

3.27.15 ImImagePlugin Module

class PIL.ImImagePlugin.ImImageFile (*fp=None, filename=None*)

Bases: PIL.ImageFile.ImageFile

format = 'IM'

format_description = 'IFUNC Image Memory'

is_animated

n_frames

seek (*frame*)

Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method raises an EOFError exception. When a sequence file is opened, the library automatically seeks to frame 0.

See *tell()*.

Parameters `frame` – Frame number, starting at 0.

Raises `EOFError` – If the call attempts to seek beyond the end of the sequence.

`tell()`

Returns the current frame number. See `seek()`.

Returns Frame number, starting with 0.

`PIL.ImImagePlugin.number(s)`

3.27.16 `ImtImagePlugin` Module

class `PIL.ImtImagePlugin.ImtImageFile` (*fp=None, filename=None*)

Bases: `PIL.ImageFile.ImageFile`

`format = 'IMT'`

`format_description = 'IM Tools'`

3.27.17 `IptcImagePlugin` Module

class `PIL.IptcImagePlugin.IptcImageFile` (*fp=None, filename=None*)

Bases: `PIL.ImageFile.ImageFile`

`field()`

`format = 'IPTC'`

`format_description = 'IPTC/NAA'`

`getint(key)`

`load()`

Load image data based on tile list

`PIL.IptcImagePlugin.dump(c)`

`PIL.IptcImagePlugin.getiptcinfo(im)`

Get IPTC information from TIFF, JPEG, or IPTC file.

Parameters `im` – An image containing IPTC data.

Returns A dictionary containing IPTC information, or `None` if no IPTC information block was found.

`PIL.IptcImagePlugin.i(c)`

3.27.18 `JpegImagePlugin` Module

`PIL.JpegImagePlugin.APP(self, marker)`

`PIL.JpegImagePlugin.COM(self, marker)`

`PIL.JpegImagePlugin.DQT(self, marker)`

class `PIL.JpegImagePlugin.JpegImageFile` (*fp=None, filename=None*)

Bases: `PIL.ImageFile.ImageFile`

draft (*mode*, *size*)

Configures the image file loader so it returns a version of the image that as closely as possible matches the given mode and size. For example, you can use this method to convert a color JPEG to greyscale while loading it.

If any changes are made, returns a tuple with the chosen mode and box with coordinates of the original image within the altered one.

Note that this method modifies the *Image* object in place. If the image has already been loaded, this method has no effect.

Note: This method is not implemented for most images. It is currently implemented only for JPEG and MPO images.

Parameters

- **mode** – The requested mode.
- **size** – The requested size.

```
format = 'JPEG'
```

```
format_description = 'JPEG (ISO 10918)'
```

```
load_djpeg ()
```

```
load_read (read_bytes)
```

internal: read more image data For premature EOF and LOAD_TRUNCATED_IMAGES adds EOI marker so libjpeg can finish decoding

```
PIL.JpegImagePlugin.SOF (self, marker)
```

```
PIL.JpegImagePlugin.Skip (self, marker)
```

```
PIL.JpegImagePlugin.convert_dict_qtables (qtables)
```

```
PIL.JpegImagePlugin.get_sampling (im)
```

```
PIL.JpegImagePlugin.jpeg_factory (fp=None, filename=None)
```

3.27.19 Jpeg2KImagePlugin Module

```
class PIL.Jpeg2KImagePlugin.Jpeg2KImageFile (fp=None, filename=None)
```

```
Bases: PIL.ImageFile.ImageFile
```

```
format = 'JPEG2000'
```

```
format_description = 'JPEG 2000 (ISO 15444)'
```

```
load ()
```

Load image data based on tile list

```
reduce
```

Returns a copy of the image reduced by *factor* times. If the size of the image is not dividable by the *factor*, the resulting size will be rounded up.

Parameters

- **factor** – A greater than 0 integer or tuple of two integers for width and height separately.
- **box** – An optional 4-tuple of ints providing the source image region to be reduced. The values must be within (0, 0, width, height) rectangle. If omitted or None, the entire source is used.

3.27.20 McIdasImagePlugin Module

```
class PIL.McIdasImagePlugin.McIdasImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.ImageFile

    format = 'MCIDAS'

    format_description = 'McIdas area file'
```

3.27.21 MicImagePlugin Module

```
class PIL.MicImagePlugin.MicImageFile (fp=None, filename=None)
    Bases: PIL.TiffImagePlugin.TiffImageFile

    format = 'MIC'

    format_description = 'Microsoft Image Composer'

    is_animated

    n_frames

    seek (frame)
        Select a given frame as current image

    tell ()
        Return the current frame number
```

3.27.22 MpegImagePlugin Module

```
class PIL.MpegImagePlugin.BitStream (fp)
    Bases: object

    next ()

    peek (bits)

    read (bits)

    skip (bits)

class PIL.MpegImagePlugin.MpegImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.ImageFile

    format = 'MPEG'

    format_description = 'MPEG'
```

3.27.23 MspImagePlugin Module

```
class PIL.MspImagePlugin.MspDecoder (mode, *args)
    Bases: PIL.ImageFile.PyDecoder

    decode (buffer)
        Override to perform the decoding process.

        Parameters buffer – A bytes object with the data to be decoded.

        Returns A tuple of (bytes consumed, errcode). If finished with decoding return <0 for the bytes
        consumed. Err codes are from ERRORS
```

```
class PIL.MspImagePlugin.MspImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.ImageFile

    format = 'MSP'

    format_description = 'Windows Paint'
```

3.27.24 PalmImagePlugin Module

```
PIL.PalmImagePlugin.build_prototype_image()
```

3.27.25 PcdImagePlugin Module

```
class PIL.PcdImagePlugin.PcdImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.ImageFile

    format = 'PCD'

    format_description = 'Kodak PhotoCD'

    load_end()
```

3.27.26 PcxImagePlugin Module

```
class PIL.PcxImagePlugin.PcxImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.ImageFile

    format = 'PCX'

    format_description = 'Paintbrush'
```

3.27.27 PdfImagePlugin Module

3.27.28 PixarImagePlugin Module

```
class PIL.PixarImagePlugin.PixarImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.ImageFile

    format = 'PIXAR'

    format_description = 'PIXAR raster image'
```

3.27.29 PngImagePlugin Module

```
PIL.PngImagePlugin.get_chunks (im, **params)
    Return a list of PNG chunks representing this image.
```

```
PIL.PngImagePlugin.is_cid()
    Matches zero or more characters at the beginning of the string.
```

```
PIL.PngImagePlugin.put_chunk (fp, cid, *data)
    Write a PNG chunk (including CRC field)
```

```
class PIL.PngImagePlugin.ChunkStream (fp)
    Bases: object
```

```

call (cid, pos, length)
    Call the appropriate chunk handler

close ()

crc (cid, data)
    Read and verify checksum

crc_skip (cid, data)
    Read checksum. Used if the C module is not present

push (cid, pos, length)

read ()
    Fetch a new chunk. Returns header information.

verify (endchunk=b'IEND')

class PIL.PngImagePlugin.PngImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.ImageFile

    format = 'PNG'

    format_description = 'Portable network graphics'

    getexif ()

    load_end ()
        internal: finished reading image data

    load_prepare ()
        internal: prepare to read PNG file

    load_read (read_bytes)
        internal: read more image data

    seek (frame)
        Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method
        raises an EOFError exception. When a sequence file is opened, the library automatically seeks to frame
        0.

        See tell().

        Parameters frame – Frame number, starting at 0.

        Raises EOFError – If the call attempts to seek beyond the end of the sequence.

    tell ()
        Returns the current frame number. See seek().

        Returns Frame number, starting with 0.

    text

    verify ()
        Verify PNG file

class PIL.PngImagePlugin.PngStream (fp)
    Bases: PIL.PngImagePlugin.ChunkStream

    check_text_memory (chunklen)

    chunk_IDAT (pos, length)

    chunk_IEND (pos, length)

    chunk_IHDR (pos, length)

```

```
chunk_PLTE (pos, length)
chunk_acTL (pos, length)
chunk_cHRM (pos, length)
chunk_eXIf (pos, length)
chunk_fcTL (pos, length)
chunk_fdAT (pos, length)
chunk_gAMA (pos, length)
chunk_iCCP (pos, length)
chunk_iTXt (pos, length)
chunk_pHYs (pos, length)
chunk_sRGB (pos, length)
chunk_tEXt (pos, length)
chunk_tRNS (pos, length)
chunk_zTXt (pos, length)
rewind()
save_rewind()
```

3.27.30 PpmImagePlugin Module

```
class PIL.PpmImagePlugin.PpmImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.ImageFile
    format = 'PPM'
    format_description = 'Pbmplus image'
```

3.27.31 PsdImagePlugin Module

```
class PIL.PsdImagePlugin.PsdImageFile (fp=None, filename=None)
    Bases: PIL.ImageFile.ImageFile
    format = 'PSD'
    format_description = 'Adobe Photoshop'
    is_animated
    load_prepare()
    n_frames
    seek (layer)
```

Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method raises an **EOFError** exception. When a sequence file is opened, the library automatically seeks to frame 0.

See `tell()`.

Parameters `frame` – Frame number, starting at 0.

Raises EOFError – If the call attempts to seek beyond the end of the sequence.

tell()

Returns the current frame number. See *seek()*.

Returns Frame number, starting with 0.

3.27.32 SgiImagePlugin Module

class PIL.SgiImagePlugin.**SGI16Decoder** (*mode, *args*)

Bases: *PIL.ImageFile.PyDecoder*

decode (*buffer*)

Override to perform the decoding process.

Parameters **buffer** – A bytes object with the data to be decoded.

Returns A tuple of (bytes consumed, errcode). If finished with decoding return <0 for the bytes consumed. Err codes are from *ERRORS*

class PIL.SgiImagePlugin.**SgiImageFile** (*fp=None, filename=None*)

Bases: *PIL.ImageFile.ImageFile*

format = 'SGI'

format_description = 'SGI Image File Format'

3.27.33 SpiderImagePlugin Module

class PIL.SpiderImagePlugin.**SpiderImageFile** (*fp=None, filename=None*)

Bases: *PIL.ImageFile.ImageFile*

convert2byte (*depth=255*)

format = 'SPIDER'

format_description = 'Spider 2D image'

is_animated

n_frames

seek (*frame*)

Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method raises an **EOFError** exception. When a sequence file is opened, the library automatically seeks to frame 0.

See *tell()*.

Parameters **frame** – Frame number, starting at 0.

Raises EOFError – If the call attempts to seek beyond the end of the sequence.

tell()

Returns the current frame number. See *seek()*.

Returns Frame number, starting with 0.

tkPhotoImage ()

PIL.SpiderImagePlugin.isInt (*f*)

PIL.SpiderImagePlugin.isSpiderHeader (*t*)

`PIL.SpiderImagePlugin.isSpiderImage` (*filename*)

`PIL.SpiderImagePlugin.loadImageSeries` (*filelist=None*)
create a list of *Image* objects for use in a montage

`PIL.SpiderImagePlugin.makeSpiderHeader` (*im*)

3.27.34 SunImagePlugin Module

```
class PIL.SunImagePlugin.SunImageFile (fp=None, filename=None)  
    Bases: PIL.ImageFile.ImageFile  
  
    format = 'SUN'  
  
    format_description = 'Sun Raster File'
```

3.27.35 TgaImagePlugin Module

```
class PIL.TgaImagePlugin.TgaImageFile (fp=None, filename=None)  
    Bases: PIL.ImageFile.ImageFile  
  
    format = 'TGA'  
  
    format_description = 'Targa'
```

3.27.36 TiffImagePlugin Module

```
class PIL.TiffImagePlugin.AppendingTiffWriter (fn, new=False)  
    Bases: object  
  
    Tags = {273, 288, 324, 519, 520, 521}  
  
    close ()  
  
    fieldSizes = [0, 1, 1, 2, 4, 8, 1, 1, 2, 4, 8, 4, 8]  
  
    finalize ()  
  
    fixIFD ()  
  
    fixOffsets (count, isShort=False, isLong=False)  
  
    goToEnd ()  
  
    newFrame ()  
  
    readLong ()  
  
    readShort ()  
  
    rewriteLastLong (value)  
  
    rewriteLastShort (value)  
  
    rewriteLastShortToLong (value)  
  
    seek (offset, whence=0)  
  
    setEndian (endian)  
  
    setup ()  
  
    skipIFDs ()
```



```

tell()
write(data)
writeLong(value)
writeShort(value)

```

```

class PIL.TiffImagePlugin.IFDRational(value, denominator=1)
    Bases: numbers.Rational

```

Implements a rational class where 0/0 is a legal value to match the in the wild use of exif rationals.
e.g., DigitalZoomRatio - 0.00/0.00 indicates that no digital zoom was used

denominator

limit_rational (*max_denominator*)

Parameters *max_denominator* – Integer, the maximum denominator value

Returns Tuple of (numerator, denominator)

numerator

```

PIL.TiffImagePlugin.ImageFileDirectory
    alias of PIL.TiffImagePlugin.ImageFileDirectory_v1

```

```

class PIL.TiffImagePlugin.ImageFileDirectory_v1(*args, **kwargs)
    Bases: PIL.TiffImagePlugin.ImageFileDirectory_v2

```

This class represents the **legacy** interface to a TIFF tag directory.

Exposes a dictionary interface of the tags in the directory:

```

ifd = ImageFileDirectory_v1()
ifd[key] = 'Some Data'
ifd.tagtype[key] = TiffTags.ASCII
print(ifd[key])
('Some Data',)

```

Also contains a dictionary of tag types as read from the tiff image file,
~*PIL.TiffImagePlugin.ImageFileDirectory_v1.tagtype*.

Values are returned as a tuple.

Deprecated since version 3.0.0.

classmethod from_v2 (*original*)

Returns an *ImageFileDirectory_v1* instance with the same data as is contained in the original *ImageFileDirectory_v2* instance.

Returns *ImageFileDirectory_v1*

tagdata

tags

to_v2 ()

Returns an *ImageFileDirectory_v2* instance with the same data as is contained in the original *ImageFileDirectory_v1* instance.

Returns *ImageFileDirectory_v2*

```

class PIL.TiffImagePlugin.ImageFileDirectory_v2(ifh=b'II*x00x00x00x00', pre-
                                                fix=None)

```

Bases: collections.abc.MutableMapping

This class represents a TIFF tag directory. To speed things up, we don't decode tags unless they're asked for.

Exposes a dictionary interface of the tags in the directory:

```
ifd = ImageFileDirectory_v2()
ifd[key] = 'Some Data'
ifd.tagtype[key] = TiffTags.ASCII
print(ifd[key])
'Some Data'
```

Individual values are returned as the strings or numbers, sequences are returned as tuples of the values.

The tiff metadata type of each item is stored in a dictionary of tag types in `~PIL.TiffImagePlugin.ImageFileDirectory_v2.tagtype`. The types are read from a tiff file, guessed from the type added, or added manually.

Data Structures:

- `self.tagtype = {}`
 - Key: numerical tiff tag number
 - **Value: integer corresponding to the data type from `~PIL.TiffTags.TYPES`**

New in version 3.0.0.

legacy_api

load (*fp*)

load_byte (*data*, *legacy_api=True*)

load_double (*data*, *legacy_api=True*)

load_float (*data*, *legacy_api=True*)

load_long (*data*, *legacy_api=True*)

load_rational (*data*, *legacy_api=True*)

load_short (*data*, *legacy_api=True*)

load_signed_byte (*data*, *legacy_api=True*)

load_signed_long (*data*, *legacy_api=True*)

load_signed_rational (*data*, *legacy_api=True*)

load_signed_short (*data*, *legacy_api=True*)

load_string (*data*, *legacy_api=True*)

load_undefined (*data*, *legacy_api=True*)

named ()

Returns dict of name:key: value

Returns the complete tag dictionary, with named tags where possible.

offset

prefix

reset ()

save (*fp*)

tobytes (*offset=0*)

```

write_byte (data)
write_double (*values)
write_float (*values)
write_long (*values)
write_rational (*values)
write_short (*values)
write_signed_byte (*values)
write_signed_long (*values)
write_signed_rational (*values)
write_signed_short (*values)
write_string (value)
write_undefined (value)

```

```

class PIL.TiffImagePlugin.TiffImageFile (fp=None, filename=None)
  Bases: PIL.ImageFile.ImageFile

  format = 'TIFF'
  format_description = 'Adobe TIFF'
  is_animated
  load ()
    Load image data based on tile list
  load_end ()
  n_frames
  seek (frame)
    Select a given frame as current image
  tell ()
    Return the current frame number

```

3.27.37 WebPImagePlugin Module

```

class PIL.WebPImagePlugin.WebPImageFile (fp=None, filename=None)
  Bases: PIL.ImageFile.ImageFile

  format = 'WEBP'
  format_description = 'WebP image'
  is_animated
  load ()
    Load image data based on tile list
  n_frames
  seek (frame)
    Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method
    raises an EOFError exception. When a sequence file is opened, the library automatically seeks to frame
    0.

```

See `tell()`.

Parameters `frame` – Frame number, starting at 0.

Raises `EOFError` – If the call attempts to seek beyond the end of the sequence.

`tell()`

Returns the current frame number. See `seek()`.

Returns Frame number, starting with 0.

3.27.38 WmfImagePlugin Module

class `PIL.WmfImagePlugin.WmfStubImageFile` (*fp=None, filename=None*)

Bases: `PIL.ImageFile.StubImageFile`

format = 'WMF'

format_description = 'Windows Metafile'

load (*dpi=None*)

Load image data based on tile list

`PIL.WmfImagePlugin.register_handler` (*handler*)

Install application-specific WMF image handler.

Parameters `handler` – Handler object.

3.27.39 XVThumbImagePlugin Module

class `PIL.XVThumbImagePlugin.XVThumbImageFile` (*fp=None, filename=None*)

Bases: `PIL.ImageFile.ImageFile`

format = 'XVThumb'

format_description = 'XV thumbnail image'

3.27.40 XbmImagePlugin Module

class `PIL.XbmImagePlugin.XbmImageFile` (*fp=None, filename=None*)

Bases: `PIL.ImageFile.ImageFile`

format = 'XBM'

format_description = 'X11 Bitmap'

3.27.41 XpmImagePlugin Module

class `PIL.XpmImagePlugin.XpmImageFile` (*fp=None, filename=None*)

Bases: `PIL.ImageFile.ImageFile`

format = 'XPM'

format_description = 'X11 Pixel Map'

load_read (*bytes*)

3.28 Internal Reference Docs

3.28.1 File Handling in Pillow

When opening a file as an image, Pillow requires a filename, `pathlib.Path` object, or a file-like object. Pillow uses the filename or `Path` to open a file, so for the rest of this article, they will all be treated as a file-like object.

The following are all equivalent:

```
from PIL import Image
import io
import pathlib

with Image.open('test.jpg') as im:
    ...

with Image.open(pathlib.Path('test.jpg')) as im2:
    ...

with open('test.jpg', 'rb') as f:
    im3 = Image.open(f)
    ...

with open('test.jpg', 'rb') as f:
    im4 = Image.open(io.BytesIO(f.read()))
    ...
```

If a filename or a path-like object is passed to Pillow, then the resulting file object opened by Pillow may also be closed by Pillow after the `Image.open()` method is called, provided the associated image does not have multiple frames.

Pillow cannot in general close and reopen a file, so any access to that file needs to be prior to the close.

Image Lifecycle

- `Image.open()` Filenames and `Path` objects are opened as a file. Metadata is read from the open file. The file is left open for further usage.
- `Image.open().load()` When the pixel data from the image is required, `load()` is called. The current frame is read into memory. The image can now be used independently of the underlying image file.

If a filename or a `Path` object was passed to `Image.open()`, then the file object was opened by Pillow and is considered to be used exclusively by Pillow. So if the image is a single-frame image, the file will be closed in this method after the frame is read. If the image is a multi-frame image, (e.g. multipage TIFF and animated GIF) the image file is left open so that `Image.open().seek()` can load the appropriate frame.

- `Image.open().close()` Closes the file and destroys the core image object. This is used in the Pillow context manager support. e.g.:

```
with Image.open('test.jpg') as img:
    ... # image operations here.
```

The lifecycle of a single-frame image is relatively simple. The file must remain open until the `load()` or `close()` function is called or the context manager exits.

Multi-frame images are more complicated. The `load()` method is not a terminal method, so it should not close the underlying file. In general, Pillow does not know if there are going to be any requests for additional data until the

caller has explicitly closed the image.

Complications

- `TiffImagePlugin` has some code to pass the underlying file descriptor into `libtiff` (if working on an actual file). Since `libtiff` closes the file descriptor internally, it is duplicated prior to passing it into `libtiff`.
- After a file has been closed, operations that require file access will fail:

```
with open('test.jpg', 'rb') as f:
    im5 = Image.open(f)
im5.load() # FAILS, closed file

with Image.open('test.jpg') as im6:
    pass
im6.load() # FAILS, closed file
```

Proposed File Handling

- `Image.open().load()` should close the image file, unless there are multiple frames.
- `Image.open().seek()` should never close the image file.
- Users of the library should use a context manager or call `Image.open().close()` on any image opened with a filename or `Path` object to ensure that the underlying file is closed.

3.28.2 Limits

This page is documentation to the various fundamental size limits in the Pillow implementation.

Internal Limits

- Image sizes cannot be negative. These are checked both in `Storage.c` and `Image.py`
- Image sizes may be 0. (Although not in 3.4)
- Maximum pixel dimensions are limited to `INT32`, or 2^{31} by the sizes in the image header.
- Individual allocations are limited to 2GB in `Storage.c`
- The 2GB allocation puts an upper limit to the `xsize` of the image of either 2^{31} for 'L' or 2^{29} for 'RGB'
- Individual memory mapped segments are limited to 2GB in `map.c` based on the overflow checks. This requires that any memory mapped image is smaller than 2GB, as calculated by `y*stride` (so 2Gpx for 'L' images, and .5Gpx for 'RGB')
- Any call to internal python size functions for buffers or strings are currently returned as `int32`, not `py_ssize_t`. This limits the maximum buffer to 2GB for operations like `frombytes` and `frombuffer`.
- This also limits the size of buffers converted using a decoder. (`decode.c:127`)

Format Size Limits

- ICO: Max size is 256x256
- Webp: 16383x16383 (underlying library size limit: <https://developers.google.com/speed/webp/docs/api>)

3.28.3 Block Allocator

Previous Design

Historically there have been two image allocators in Pillow: `ImagingAllocateBlock` and `ImagingAllocateArray`. The first works for images smaller than 16MB of data and allocates one large chunk of memory of `im->linesize * im->ysize` bytes. The second works for large images and makes one allocation for each scan line of size `im->linesize` bytes. This makes for a very sharp transition between one allocation and potentially thousands of small allocations, leading to unpredictable performance penalties around the transition.

New Design

`ImagingAllocateArray` now allocates space for images as a chain of blocks with a maximum size of 16MB. If there is a memory allocation error, it falls back to allocating a 4KB block, or at least one scan line. This is now the default for all internal allocations.

`ImagingAllocateBlock` is now only used for those cases when we are specifically requesting a single segment of memory for sharing with other code.

Memory Pools

There is now a memory pool to contain a supply of recently freed blocks, which can then be reused without going back to the OS for a fresh allocation. This caching of free blocks is currently disabled by default, but can be enabled and tweaked using three environment variables:

- `PILLOW_ALIGNMENT`, in bytes. Specifies the alignment of memory allocations. Valid values are powers of 2 between 1 and 128, inclusive. Defaults to 1.
- `PILLOW_BLOCK_SIZE`, in bytes, K, or M. Specifies the maximum block size for `ImagingAllocateArray`. Valid values are integers, with an optional *k* or *m* suffix. Defaults to 16M.
- `PILLOW_BLOCKS_MAX` Specifies the number of freed blocks to retain to fill future memory requests. Any freed blocks over this threshold will be returned to the OS immediately. Defaults to 0.

Porting existing PIL-based code to Pillow

Pillow is a functional drop-in replacement for the Python Imaging Library.

PIL is Python 2 only. Pillow dropped support for Python 2 in Pillow 7.0. So if you would like to run the latest version of Pillow, you will first and foremost need to port your code from Python 2 to 3.

To run your existing PIL-compatible code with Pillow, it needs to be modified to import the `Image` module from the `PIL` namespace *instead* of the global namespace. Change this:

```
import Image
```

to this:

```
from PIL import Image
```

The `_imaging` module has been moved. You can now import it like this:

```
from PIL.Image import core as _imaging
```

The image plugin loading mechanism has changed. Pillow no longer automatically imports any file in the Python path with a name ending in `ImagePlugin.py`. You will need to import your image plugin manually.

Pillow will raise an exception if the core extension can't be loaded for any reason, including a version mismatch between the Python and extension code. Previously PIL allowed Python only code to run if the core extension was not available.

5.1 Goals

The fork author's goal is to foster and support active development of PIL through:

- Continuous integration testing via [Travis CI](#), [AppVeyor](#) and [GitHub Actions](#)
- Publicized development activity on [GitHub](#)
- Regular releases to the [Python Package Index](#)

5.2 License

Like PIL, Pillow is licensed under the open source [PIL Software License](#)

5.3 Why a fork?

PIL is not [setuptools](#) compatible. Please see [this Image-SIG post](#) for a more detailed explanation. Also, PIL's current bi-yearly (or greater) release schedule is too infrequent to accommodate the large number and frequency of issues reported.

5.4 What about PIL?

Note: Prior to Pillow 2.0.0, very few image code changes were made. Pillow 2.0.0 added Python 3 support and includes many bug fixes from many contributors.

As more time passes since the last PIL release (1.1.7 in 2009), the likelihood of a new PIL release decreases. However, we've yet to hear an official "PIL is dead" announcement. So if you still want to support PIL, please [report issues here first](#), then [open corresponding Pillow tickets here](#).

Please provide a link to the first ticket so we can track the issue(s) upstream.

Note: Contributors please include release notes as needed or appropriate with your bug fixes, feature additions and tests.

6.1 7.1.2

6.1.1 Fix another regression seeking PNG files

This fixes a regression introduced in 7.1.0 when adding support for APNG files.

When calling `seek(n)` on a regular PNG where $n > 0$, it failed to raise an `EOFError` as it should have done, resulting in:

```
AttributeError: 'NoneType' object has no attribute 'read'
```

Pillow 7.1.2 now raises the correct exception.

6.2 7.1.1

6.2.1 Fix regression seeking PNG files

This fixes a regression introduced in 7.1.0 when adding support for APNG files when calling `seek` and `tell`:

```
>>> from PIL import Image
>>> with Image.open("Tests/images/hopper.png") as im:
...     im.seek(0)
...
Traceback (most recent call last):
```

(continues on next page)

(continued from previous page)

```
File "<stdin>", line 2, in <module>
File "/Library/Frameworks/Python.framework/Versions/3.8/lib/python3.8/site-packages/
↳PIL/PngImagePlugin.py", line 739, in seek
    if not self._seek_check(frame):
File "/Library/Frameworks/Python.framework/Versions/3.8/lib/python3.8/site-packages/
↳PIL/ImageFile.py", line 306, in _seek_check
    return self.tell() != frame
File "/Library/Frameworks/Python.framework/Versions/3.8/lib/python3.8/site-packages/
↳PIL/PngImagePlugin.py", line 827, in tell
    return self.__frame
AttributeError: 'PngImageFile' object has no attribute '_PngImageFile__frame'
>>>
```

6.3 7.1.0

6.3.1 API Changes

Allow saving of zero quality JPEG images

If no quality was specified when saving a JPEG, Pillow internally used a value of zero to indicate that the default quality should be used. However, this removed the ability to actually save a JPEG with zero quality. This has now been resolved.

```
from PIL import Image
im = Image.open("hopper.jpg")
im.save("out.jpg", quality=0)
```

6.3.2 API Additions

New channel operations

Three new channel operations have been added: `soft_light()`, `hard_light()` and `overlay()`.

PILLOW_VERSION constant

PILLOW_VERSION has been re-added but is deprecated and will be removed in a future release. Use `__version__` instead.

It was initially removed in Pillow 7.0.0, but brought back in 7.1.0 to give projects more time to upgrade.

Reading JPEG comments

When opening a JPEG image, the comment may now be read into `info`.

Support for different charset encodings in PcfFontFile

Previously `PcfFontFile` output only bitmap PIL fonts with ISO 8859-1 encoding, even though the PCF format supports Unicode, making it hard to work with Pillow with bitmap fonts in languages which use different character sets.

Now it's possible to set a different charset encoding in `PcfFontFile`'s class constructor. By default, it generates a PIL font file with ISO 8859-1 as before. The generated PIL font file still contains up to 256 characters, but the character set is different depending on the selected encoding.

To use such a font with `ImageDraw.text`, call it with a bytes object with the same encoding as the font file.

X11 ImageGrab.grab()

Support has been added for `ImageGrab.grab()` on Linux using the X server with the XCB library.

An optional `xdisplay` parameter has been added to select the X server, with the default value of `None` using the default X server.

Passing a different value on Windows or macOS will force taking a snapshot using the selected X server; pass an empty string to use the default X server. XCB support is not included in pre-compiled wheels for Windows and macOS.

6.3.3 Other Changes

If present, only use alpha channel for bounding box

When the `getbbox()` method calculates the bounding box, for an RGB image it trims black pixels. Similarly, for an RGBA image it would trim black transparent pixels. This is now changed so that if an image has an alpha channel (RGBA, RGBa, PA, LA, La), any transparent pixels are trimmed.

Improved APNG support

Added support for reading and writing Animated Portable Network Graphics (APNG) images. The PNG plugin now supports using the `seek()` method and the `Iterator` class to read APNG frame sequences. The PNG plugin also now supports using the `append_images` argument to write APNG frame sequences. See *APNG sequences* for further details.

6.4 7.0.0

6.4.1 Backwards Incompatible Changes

Python 2.7

Pillow has dropped support for Python 2.7, which reached end-of-life on 2020-01-01.

PILLOW_VERSION constant

`PILLOW_VERSION` has been removed. Use `__version__` instead.

PIL.*ImagePlugin.__version__ attributes

The version constants of individual plugins have been removed. Use `PIL.__version__` instead.

Removed	Removed	Removed
BmpImagePlugin. __version__	Jpeg2KImagePlugin. __version__	PngImagePlugin. __version__
CurImagePlugin. __version__	JpegImagePlugin. __version__	PpmImagePlugin. __version__
DcxImagePlugin. __version__	McIdasImagePlugin. __version__	PsdImagePlugin. __version__
EpsImagePlugin. __version__	MicImagePlugin. __version__	SgiImagePlugin. __version__
FliImagePlugin. __version__	MpegImagePlugin. __version__	SunImagePlugin. __version__
FpxImagePlugin. __version__	MpoImagePlugin. __version__	TgaImagePlugin. __version__
GdImageFile. __version__	MspImagePlugin. __version__	TiffImagePlugin. __version__
GifImagePlugin. __version__	PalmImagePlugin. __version__	WmfImagePlugin. __version__
IcoImagePlugin. __version__	PcdImagePlugin. __version__	XbmImagePlugin. __version__
ImImagePlugin. __version__	PcxImagePlugin. __version__	XpmImagePlugin. __version__
ImtImagePlugin. __version__	PdfImagePlugin. __version__	XVThumbImagePlugin. __version__
IptcImagePlugin. __version__	PixarImagePlugin. __version__	

PyQt4 and PySide

Qt 4 reached end-of-life on 2015-12-19. Its Python bindings are also EOL: PyQt4 since 2018-08-31 and PySide since 2015-10-14.

Support for PyQt4 and PySide has been removed from ImageQt. Please upgrade to PyQt5 or PySide2.

Setting the size of TIFF images

Setting the size of a TIFF image directly (eg. `im.size = (256, 256)`) throws an error. Use `Image.resize` instead.

Default resampling filter

The default resampling filter has been changed to the high-quality convolution `Image.BICUBIC` instead of `Image.NEAREST`, for the `resize()` method and the `pad()`, `scale()` and `fit()` functions. `Image.NEAREST` is still always used for images in “P” and “1” modes. See [Filters](#) to learn the difference. In short, `Image.NEAREST` is a very fast filter, but simple and low-quality.

Image.draft() return value

If the `draft()` method has no effect, it returns `None`. If it does have an effect, then it previously returned the image itself. However, unlike other [chain methods](#), `draft()` does not return a modified version of the image, but modifies it in-place. So instead, if `draft()` has an effect, Pillow will now return a tuple of the image mode and

a co-ordinate box. The box is the original coordinates in the bounds of resulting image. This may be useful in a subsequent `resize()` call.

6.4.2 API Additions

Custom unidentified image error

Pillow will now throw a custom `UnidentifiedImageError` when an image cannot be identified. For backwards compatibility, this will inherit from `IOError`.

New argument `reducing_gap` for `Image.resize()` and `Image.thumbnail()` methods

Speeds up resizing by resizing the image in two steps. The bigger `reducing_gap`, the closer the result to the fair resampling. The smaller `reducing_gap`, the faster resizing. With `reducing_gap` greater or equal to 3.0, the result is indistinguishable from fair resampling.

The default value for `resize()` is `None`, which means that the optimization is turned off by default.

The default value for `thumbnail()` is 2.0, which is very close to fair resampling while still being faster in many cases. In addition, the same gap is applied when `thumbnail()` calls `draft()`, which may greatly improve the quality of JPEG thumbnails. As a result, `thumbnail()` in the new version provides equally high speed and high quality from any source (JPEG or arbitrary images).

New `Image.reduce()` method

`reduce()` is a highly efficient operation to reduce an image by integer times. Normally, it shouldn't be used directly. Used internally by `resize()` and `thumbnail()` methods to speed up resize when a new argument `reducing_gap` is set.

Loading WMF images at a given DPI

On Windows, Pillow can read WMF files, with a default DPI of 72. An image can now also be loaded at another resolution:

```
from PIL import Image
with Image.open("drawing.wmf") as im:
    im.load(dpi=144)
```

6.4.3 Other Changes

`Image.__del__`

Implicitly closing the image's underlying file in `Image.__del__` has been removed. Use a context manager or call `close()` instead to close the file in a deterministic way.

Previous method:

```
im = Image.open("hopper.png")
im.save("out.jpg")
```

Use instead:

```
with Image.open("hopper.png") as im:  
    im.save("out.jpg")
```

Better thumbnail geometry

When calculating the new dimensions in `thumbnail()`, round to the nearest integer, instead of always rounding down. This better preserves the original aspect ratio.

When the image width or height is not divisible by 8 the last row and column in the image get the correct weight after JPEG DCT scaling.

6.5 6.2.2

6.5.1 Security

This release addresses several security problems.

CVE-2019-19911 is regarding FPX images. If an image reports that it has a large number of bands, a large amount of resources will be used when trying to process the image. This is fixed by limiting the number of bands to those usable by Pillow.

Buffer overruns were found when processing an SGI (CVE-2020-5311), PCX (CVE-2020-5312) or FLI image (CVE-2020-5313). Checks have been added to prevent this.

CVE-2020-5310: Overflow checks have been added when calculating the size of a memory block to be reallocated in the processing of a TIFF image.

6.6 6.2.1

6.6.1 API Changes

Deprecations

Python 2.7

Python 2.7 reaches end-of-life on 2020-01-01.

Pillow 7.0.0 will be released on 2020-01-01 and will drop support for Python 2.7, making Pillow 6.2.x the last release series to support Python 2.

6.6.2 Other Changes

Support added for Python 3.8

Pillow 6.2.1 supports Python 3.8.

6.7 6.2.0

6.7.1 API Additions

Text stroking

`stroke_width` and `stroke_fill` arguments have been added to text drawing operations. They allow text to be outlined, setting the width of the stroke and the color respectively. If not provided, `stroke_fill` will default to the `fill` parameter.

```
from PIL import Image, ImageDraw, ImageFont

font = ImageFont.truetype("Tests/fonts/FreeMono.ttf", 40)
font.getsize_multiline("A", stroke_width=2)
font.getsize("ABC\nAaaa", stroke_width=2)


im = Image.new("RGB", (100, 100))
draw = ImageDraw.Draw(im)
draw.textsize("A", font, stroke_width=2)
draw.multiline_textsize("ABC\nAaaa", font, stroke_width=2)
draw.text((10, 10), "A", "#f00", font, stroke_width=2, stroke_fill="#0f0")
draw.multiline_text((10, 10), "A\nB", "#f00", font,
                    stroke_width=2, stroke_fill="#0f0")
```

For example,

```
from PIL import Image, ImageDraw, ImageFont

im = Image.new("RGB", (120, 130))
draw = ImageDraw.Draw(im)
font = ImageFont.truetype("Tests/fonts/FreeMono.ttf", 120)
draw.text((10, 10), "A", "#f00", font, stroke_width=2, stroke_fill="#0f0")
```

creates the following image:



ImageGrab on multi-monitor Windows

An `all_screens` argument has been added to `ImageGrab.grab`. If `True`, all monitors will be included in the created image.

6.7.2 API Changes

Image.getexif

To allow for lazy loading of Exif data, `Image.getexif()` now returns a shared instance of `Image.Exif`.

Deprecations

Image.frombuffer

There has been a longstanding warning that the defaults of `Image.frombuffer` may change in the future for the “raw” decoder. The change will now take place in Pillow 7.0.

6.7.3 Security

This release catches several buffer overruns, as well as addressing CVE-2019-16865. The CVE is regarding DOS problems, such as consuming large amounts of memory, or taking a large amount of time to process an image.

In `RawDecode.c`, an error is now thrown if `skip` is calculated to be less than zero. It is intended to skip padding between lines, not to go backwards.

In `PsdImagePlugin`, if the combined sizes of the individual parts is larger than the declared size of the extra data field, then it looked for the next layer by seeking backwards. This is now corrected by seeking to (the start of the layer + the size of the extra data field) instead of (the read parts of the layer + the rest of the layer).

Decompression bomb checks have been added to GIF and ICO formats.

An error is now raised if a TIFF dimension is a string, rather than trying to perform operations on it.

6.7.4 Other Changes

Removed bdist_wininst .exe installers

.exe installers fell out of favour with PEP 527, and will be deprecated in Python 3.8. Pillow will no longer be distributing them. Wheels should be used instead.

Flags for libwebp in wheels

When building `libwebp` for inclusion in wheels, Pillow now adds the `-O3` and `-DNDEBUG` CFLAGS. These flags would be used by default if building `libwebp` without debugging, and using them fixes a significant decrease in speed when a wheel-installed copy of Pillow performs `libwebp` operations.

6.8 6.1.0

6.8.1 Deprecations

Image.__del__

Deprecated since version 6.1.0.

Implicitly closing the image’s underlying file in `Image.__del__` has been deprecated. Use a context manager or call `Image.close()` instead to close the file in a deterministic way.

Deprecated:

```
im = Image.open("hopper.png")
im.save("out.jpg")
```

Use instead:

```
with Image.open("hopper.png") as im:
    im.save("out.jpg")
```

6.8.2 API Additions

Image.entropy

Calculates and returns the entropy for the image. A bilevel image (mode “1”) is treated as a greyscale (“L”) image by this method. If a mask is provided, the method employs the histogram for those parts of the image where the mask image is non-zero. The mask image must have the same size as the image, and be either a bi-level image (mode “1”) or a greyscale image (“L”).

ImageGrab.grab

An optional `include_layered_windows` parameter has been added to `ImageGrab.grab`, defaulting to `False`. If true, layered windows will be included in the resulting image on Windows.

ImageSequence.all_frames

A new method to facilitate applying a given function to all frames in an image, or to all frames in a list of images. The frames are returned as a list of separate images. For example, `ImageSequence.all_frames(im, lambda im_frame: im_frame.rotate(90))` could be used to return all frames from an image, each rotated 90 degrees.

Variation fonts

Variation fonts are now supported, allowing for different styles from the same font file. `ImageFont.FreeTypeFont` has four new methods, `PIL.ImageFont.FreeTypeFont.get_variation_names()` and `PIL.ImageFont.FreeTypeFont.set_variation_by_name()` for using named styles, and `PIL.ImageFont.FreeTypeFont.get_variation_axes()` and `PIL.ImageFont.FreeTypeFont.set_variation_by_axes()` for using font axes instead. An `IOError` will be raised if the font is not a variation font. FreeType 2.9.1 or greater is required.

6.8.3 Other Changes

ImageTk.getimage

This function is now supported. It returns the contents of an `ImageTk.PhotoImage` as an `RGBA Image.Image` instance.

Image quality for JPEG compressed TIFF

The TIFF encoder accepts a `quality` parameter for `jpeg` compressed TIFF files. A value from 0 (worst) to 100 (best) controls the image quality, similar to the JPEG encoder. The default is 75. For example:

```
im.save("out.tif", compression="jpeg", quality=85)
```

Improve encoding of TIFF tags

The TIFF encoder supports more types, especially arrays. This is required for the GeoTIFF format which encodes geospatial information.

- Pass `tagtype` from `v2` directory to `libtiff` encoder, instead of autodetecting type.
- Use explicit types eg. `uint32_t` for `TIFF_LONG` to fix issues on platforms with 64-bit longs.
- Add support for multiple values (arrays). Requires type in `v2` directory and values must be passed as a tuple.
- Add support for signed types eg. `TIFFTypes.TIFF_SIGNED_SHORT`.

Respect `PKG_CONFIG` environment variable when building

This variable is commonly used by other build systems and using it can help with cross-compiling. Falls back to `pkg-config` as before.

Top-to-bottom complex text rendering

Drawing text in the ‘`ttb`’ direction with `ImageFont` has been significantly improved and requires `Raqm` 0.7 or greater.

6.9 6.0.0

6.9.1 Backwards Incompatible Changes

Python 3.4 dropped

Python 3.4 is EOL since 2019-03-16 and no longer supported. We will not be creating binaries, testing, or retaining compatibility with this version. The final version of Pillow for Python 3.4 is 5.4.1.

Removed deprecated `PIL.OleFileIO`

`PIL.OleFileIO` was removed as a vendored file and in Pillow 4.0.0 (2017-01) in favour of the upstream `olefile` Python package, and replaced with an `ImportError`. The deprecated file has now been removed from Pillow. If needed, install from PyPI (eg. `pip install olefile`).

Removed deprecated `ImageOps` functions

Several undocumented functions in `ImageOps` were deprecated in Pillow 4.3.0 (2017-10) and have now been removed: `gaussian_blur`, `gblur`, `unsharp_mask`, `usm` and `box_blur`. Use the equivalent operations in `ImageFilter` instead.

Removed deprecated VERSION

VERSION (the old PIL version, always 1.1.7) has been removed. Use `__version__` instead.

6.9.2 API Changes

Deprecations

Python 2.7

Python 2.7 reaches end-of-life on 2020-01-01.

Pillow 7.0.0 will be released on 2020-01-01 and will drop support for Python 2.7, making Pillow 6.x the last series to support Python 2.

PyQt4 and PySide

Qt 4 reached end-of-life on 2015-12-19. Its Python bindings are also EOL: PyQt4 since 2018-08-31 and PySide since 2015-10-14.

Support for PyQt4 and PySide has been deprecated from `ImageQt` and will be removed in a future version. Please upgrade to PyQt5 or PySide2.

PIL.*ImagePlugin.__version__ attributes

These version constants have been deprecated and will be removed in a future version.

- `BmpImagePlugin.__version__`
- `CurImagePlugin.__version__`
- `DcxImagePlugin.__version__`
- `EpsImagePlugin.__version__`
- `FliImagePlugin.__version__`
- `FpxImagePlugin.__version__`
- `GdImageFile.__version__`
- `GifImagePlugin.__version__`
- `IcoImagePlugin.__version__`
- `ImImagePlugin.__version__`
- `ImtImagePlugin.__version__`
- `IptcImagePlugin.__version__`
- `Jpeg2KImagePlugin.__version__`
- `JpegImagePlugin.__version__`
- `McIDASImagePlugin.__version__`
- `MicImagePlugin.__version__`
- `MpegImagePlugin.__version__`

- `MpoImagePlugin.__version__`
- `MspImagePlugin.__version__`
- `PalmImagePlugin.__version__`
- `PcdImagePlugin.__version__`
- `PcxImagePlugin.__version__`
- `PdfImagePlugin.__version__`
- `PixarImagePlugin.__version__`
- `PngImagePlugin.__version__`
- `PpmImagePlugin.__version__`
- `PsdImagePlugin.__version__`
- `SgiImagePlugin.__version__`
- `SunImagePlugin.__version__`
- `TgaImagePlugin.__version__`
- `TiffImagePlugin.__version__`
- `WmfImagePlugin.__version__`
- `XbmImagePlugin.__version__`
- `XpmImagePlugin.__version__`
- `XVThumbImagePlugin.__version__`

Use `PIL.__version__` instead.

ImageCms.CmsProfile attributes

Some attributes in `ImageCms.CmsProfile` have been deprecated since Pillow 3.2.0. From 6.0.0, they issue a `DeprecationWarning`:

Deprecated	Use instead
<code>color_space</code>	<code>Padded xcolor_space</code>
<code>pcs</code>	<code>Padded connection_space</code>
<code>product_copyright</code>	<code>Unicode copyright</code>
<code>product_desc</code>	<code>Unicode profile_description</code>
<code>product_description</code>	<code>Unicode profile_description</code>
<code>product_manufacturer</code>	<code>Unicode manufacturer</code>
<code>product_model</code>	<code>Unicode model</code>

MIME type improvements

Previously, all JPEG2000 images had the MIME type “`image/jpx`”. This has now been corrected. After the file format drivers have been loaded, `Image.MIME["JPEG2000"]` will return “`image/jp2`”. `ImageFile.get_format_mimetype` will return “`image/jpx`” if a JPX profile is present, or “`image/jp2`” otherwise.

Previously, all SGI images had the MIME type “`image/rgb`”. This has now been corrected. After the file format drivers have been loaded, `Image.MIME["SGI"]` will return “`image/sgi`”. `ImageFile.get_format_mimetype` will return “`image/rgb`” if RGB image data is present, or “`image/sgi`” otherwise.

MIME types have been added to the PPM format. After the file format drivers have been loaded, `Image.MIME["PPM"]` will now return the generic “image/x-portable-anymap”. `ImageFile.get_format_mimetype` will return a MIME type specific to the color type.

The TGA, PCX and ICO formats also now have MIME types: “image/x-tga”, “image/x-pcx” and “image/x-icon” respectively.

6.9.3 API Additions

DIB file format

Pillow now supports reading and writing the Device Independent Bitmap file format.

Image.quantize

The `dither` option is now a customisable parameter (was previously hardcoded to 1). This parameter takes the same values used in `convert()`.

New language parameter

These text-rendering functions now accept a language parameter to request language-specific glyphs and ligatures from the font:

- `ImageDraw.ImageDraw.multiline_text()`
- `ImageDraw.ImageDraw.multiline_textsize()`
- `ImageDraw.ImageDraw.text()`
- `ImageDraw.ImageDraw.textsize()`
- `ImageFont.ImageFont.getmask()`
- `ImageFont.ImageFont.getsize_multiline()`
- `ImageFont.ImageFont.getsize()`

Added EXIF class

`getexif()` has been added, which returns an `Exif` instance. Values can be retrieved and set like a dictionary. When saving JPEG, PNG or WEBP, the instance can be passed as an `exif` argument to include any changes in the output image.

Added ImageOps.exif_transpose

`exif_transpose()` returns a copy of an image, transposed according to its EXIF Orientation tag.

PNG EXIF data

EXIF data can now be read from and saved to PNG images. However, unlike other image formats, EXIF data is not guaranteed to be present in `info` until `load()` has been called.

6.9.4 Other Changes

Reading new DDS image format

Pillow can now read uncompressed RGB data from DDS images.

Reading TIFF with old-style JPEG compression

Added support reading TIFF files with old-style JPEG compression through LibTIFF. All YCbCr TIFF images are now always read as RGB.

TIFF compression codecs

Support has been added for the LZMA, Zstd and WebP TIFF compression codecs.

Improved support for transposing I;16 images

I;16, I;16L and I;16B are now supported image modes for all *transpose()* operations.

6.10 5.4.1

This release fixes regressions in 5.4.0.

6.10.1 Installation on Termux

A change to the way Pillow detects libraries during installed prevented installation on Termux, which does not have `/sbin/ldconfig`. This is now fixed.

6.10.2 PNG: Handle IDAT chunks after image end

Some PNG images have multiple IDAT chunks. In some cases, Pillow will stop reading image data before the IDAT chunks finish. A regression caused an `EOFError` exception when previously there was none. This is now fixed, and file reading continues in case there are subsequent text chunks.

6.10.3 PNG: MIME type

The addition of limited APNG support to the PNG plugin also overwrote the MIME type for PNG files, causing “image/apng” to be returned as the MIME type of both APNG and PNG files. This has been fixed so the MIME type of PNG files is “image/png”.

6.10.4 File closing

A regression caused an unsupported image file to report a `ValueError: seek of closed file` exception instead of an `OSError`. This has been fixed by ensuring that image plugins only close their internal `__fp` if they are not the same as `ImageFile`'s `fp`, allowing each to manage their own file pointers.

6.11 5.4.0

6.11.1 API Changes

APNG extension to PNG plugin

Animated Portable Network Graphics (APNG) images are not fully supported but can be opened via the PNG plugin to get some basic info:

```
im = Image.open("image.apng")
print(im.mode) # "RGBA"
print(im.size) # (245, 245)
im.show() # Shows a single frame
```

Check for libjpeg-turbo

You can check if Pillow has been built against the libjpeg-turbo version of the libjpeg library:

```
from PIL import features
features.check_feature("libjpeg_turbo") # True or False
```

Negative indexes in pixel access

When accessing individual image pixels, negative indexes are now also accepted. For example, to get or set the farthest pixel in the lower right of an image:

```
px = im.load()
print(px[-1, -1])
px[-1, -1] = (0, 0, 0)
```

New custom TIFF tags

TIFF images can now be saved with custom integer, float and string TIFF tags:

```
im = Image.new("RGB", (200, 100))
custom = {
    37000: 4,
    37001: 4.2,
    37002: "custom tag value",
    37003: u"custom tag value",
    37004: b"custom tag value",
}
im.save("output.tif", tiffinfo=custom)

im2 = Image.open("output.tif")
print(im2.tag_v2[37000]) # 4
print(im2.tag_v2[37002]) # "custom tag value"
print(im2.tag_v2[37004]) # b"custom tag value"
```

6.11.2 Other Changes

ImageOps.fit

Now uses one `resize` operation with `box` parameter internally instead of a `crop` and `scale` operations sequence. This improves the performance and accuracy of cropping since the `box` parameter accepts float values.

6.12 5.3.0

6.12.1 API Changes

Image size

If you attempt to set the size of an image directly, e.g. `im.size = (100, 100)`, you will now receive an `AttributeError`. This is not about removing existing functionality, but instead about raising an explicit error to prevent later consequences. The `resize` method is the correct way to change an image's size.

The exceptions to this are:

- The ICO and ICNS image formats, which use `im.size = (100, 100)` to select a subimage.
- The TIFF image format, which now has a `DeprecationWarning` for this action, as direct image size setting was previously necessary to work around an issue with tile extents.

6.12.2 API Additions

Added line width parameter to rectangle and ellipse-based shapes

An optional `line width` parameter has been added to `ImageDraw.Draw.arc`, `chord`, `ellipse`, `pieslice` and `rectangle`.

Curved joints for line sequences

`ImageDraw.Draw.line` draws a line, or lines, between points. Previously, when multiple points are given, for a larger `width`, the joints between these lines looked unsightly. There is now an additional optional argument, `joint`, defaulting to `None`. When it is set to `curved`, the joints between the lines will become rounded.

ImageOps.colorize

Previously `ImageOps.colorize` only supported two-color mapping with `black` and `white` arguments being mapped to 0 and 255 respectively. Now it supports three-color mapping with the optional `mid` parameter, and the positions for all three color arguments can each be optionally specified (`blackpoint`, `whitepoint` and `midpoint`). For example, with all optional arguments:

```
ImageOps.colorize(im, black=(32, 37, 79), white='white', mid=(59, 101, 175),
                  blackpoint=15, whitepoint=240, midpoint=100)
```

ImageOps.pad

While `ImageOps.fit` allows users to crop images to a requested aspect ratio and size, new method `ImageOps.pad` pads images to fill a requested aspect ratio and size, filling new space with a provided `color` and positioning the image within the new area through a `centering` argument.

6.12.3 Other Changes

Added support for reading tiled TIFF images through LibTIFF. Compressed TIFF images are now read through LibTIFF.

RGB WebP images are now read as RGB mode, rather than RGBX.

6.13 5.2.0

6.13.1 API Changes

Deprecations

These version constants have been deprecated. `VERSION` will be removed in Pillow 6.0.0, and `PILLOW_VERSION` will be removed after that.

- `PIL.VERSION` (old PIL version 1.1.7)
- `PIL.PILLOW_VERSION`
- `PIL.Image.VERSION`
- `PIL.Image.PILLOW_VERSION`

Use `PIL.__version__` instead.

6.13.2 API Additions

3D color lookup tables

Support for 3D color lookup table transformations has been added.

- https://en.wikipedia.org/wiki/3D_lookup_table

`Color3DLUT.generate` transforms 3-channel pixels using the values of the channels as coordinates in the 3D lookup table and interpolating the nearest elements.

It allows you to apply almost any color transformation in constant time by using pre-calculated decimated tables.

`Color3DLUT.transform()` allows altering table values with a callback.

If NumPy is installed, the performance of argument conversion is dramatically improved when a source table supports buffer interface (NumPy `&&` arrays in Python `>= 3`).

ImageColor.getrgb

Previously `Image.rotate` only supported HSL color strings. Now HSB and HSV strings are also supported, as well as float values. For example, `ImageColor.getrgb("hsv(180,100%,99.5%))"`.

ImageFile.get_format_mimetype

`ImageFile.get_format_mimetype` has been added to return the MIME type of an image file, where available. For example, `Image.open("hopper.jpg").get_format_mimetype()` returns `"image/jpeg"`.

ImageFont.getsize_multiline

A new method to return the size of multiline text, for example `font.getsize_multiline("ABC\nAaaa")`

Image.rotate

A new named parameter, `fillcolor`, has been added to `Image.rotate`. This color specifies the background color to use in the area outside the rotated image. This parameter takes the same color specifications as used in `Image.new`.

TGA file format

Pillow can now read and write LA data (in addition to L, P, RGB and RGBA), and write RLE data (in addition to uncompressed).

6.13.3 Other Changes

Support added for Python 3.7

Pillow 5.2 supports Python 3.7.

Build macOS wheels with Xcode 6.4, supporting older macOS versions

The macOS wheels for Pillow 5.1.0 were built with Xcode 9.2, meaning 10.12 Sierra was the lowest supported version. Prior to Pillow 5.1.0, Xcode 8 was used, supporting El Capitan 10.11.

Instead, Pillow 5.2.0 is built with the oldest available Xcode 6.4 to support at least 10.10 Yosemite.

Fix _i2f compilation with some GCC versions

For example, this allows compilation with GCC 4.8 on NetBSD.

Resolve confusion getting PIL / Pillow version string

Re: “version constants deprecated” listed above, as user gnbl notes in #3082:

- it’s confusing that `PIL.VERSION` returns the version string of the former PIL instead of Pillow’s
- there does not seem to be documentation on this version number (why this, will it ever change, ..) e.g. at <https://pillow.readthedocs.io/en/5.1.x/about.html#why-a-fork>
- it’s confusing that `PIL.version` is a module and does not return the version information directly or hints on how to get it
- the package information header is essentially useless (placeholder, does not even mention Pillow, nor the version)

- `PIL._version` module documentation comment could explain how to access the version information

We have attempted to resolve these issues in #3083, #3090 and #3218.

6.14 5.1.0

6.14.1 New File Format

BLP File Format

Pillow now supports reading the BLP “Blizzard Mipmap” file format used for tiles in Blizzard’s engine.

6.14.2 API Changes

Optional channels for TIFF files

Pillow can now open TIFF files with base modes of `RGB`, `YCbCr`, and `CMYK` with up to 6 8-bit channels, discarding any extra channels if the content is tagged as `UNSPECIFIED`. Pillow still does not store more than 4 8-bit channels of image data.

Append to PDF Files

Images can now be appended to PDF files in place by passing in `append=True` when saving the image.

6.14.3 Other Changes

WebP memory leak

A memory leak when opening `WebP` files has been fixed.

6.15 5.0.0

6.15.1 Backwards Incompatible Changes

Python 3.3 Dropped

Python 3.3 is EOL and no longer supported due to moving testing from `nose`, which is deprecated, to `pytest`, which doesn’t support Python 3.3. We will not be creating binaries, testing, or retaining compatibility with this version. The final version of Pillow for Python 3.3 is 4.3.0.

Decompression Bombs now raise Exceptions

Pillow has previously emitted warnings for images that are unexpectedly large and may be a denial of service. These warnings are now upgraded to `DecompressionBombErrors` for images that are twice the size of images that trigger the `DecompressionBombWarning`. The default threshold is 128Mpx, or 0.5GB for an `RGB` or `RGBA` image. This can be disabled or changed by setting `Image.MAX_IMAGE_PIXELS = None`.

Scripts

The scripts formerly installed by Pillow have been split into a separate package, `pillow-scripts`, living at <https://github.com/python-pillow/pillow-scripts>.

6.15.2 API Changes

OleFileIO.py

The `olefile` module is no longer a required dependency when installing Pillow. Support for plugins requiring `olefile` will not be loaded if it is not installed. This allows library consumers to avoid installing this dependency if they choose. Some library consumers have little interest in the format support and would like to keep dependencies to a minimum.

Further, the vendored version was removed in Pillow 4.0.0 and replaced with a deprecation warning that `PIL.OleFileIO` would be removed in a future version. This warning has been upgraded to an import error pending future removal.

Check parameter on `_save`

Several image plugins supported a named `check` parameter on their nominally private `_save` method to preflight if the image could be saved in that format. That parameter has been removed.

6.15.3 API Additions

`Image.transform`

A new named parameter, `fillcolor`, has been added to `Image.transform`. This color specifies the background color to use in the area outside the transformed area in the output image. This parameter takes the same color specifications as used in `Image.new`.

GIF Disposal

Multiframe GIF images now take an optional `disposal` parameter to specify the disposal option for changed pixels.

6.15.4 Other Changes

Compressed TIFF Images

Previously, there were some compression modes (JPEG, Packbits, and LZW) that were supported with Pillow's internal TIFF decoder. All compressed TIFFs are now read using the `libtiff` decoder, as it implements the compression schemes more correctly.

Libraqm is now Dynamically Linked

The `libraqm` dependency for complex text scripts is now linked dynamically at runtime rather than at packaging time. This allows us to release binaries with support for `libraqm` if it is installed on the user's machine.

Source Layout Changes

The Pillow source is now stored within the `src` directory of the distribution. This prevents accidental imports of the PIL directory when running Python from the project directory.

Setup.py Changes

Multiarch support on Linux should be more robust, especially on Debian derivatives on ARM platforms. Debian's multiarch platform configuration is run in preference to the sniffing of machine platform and architecture.

6.16 4.3.0

6.16.1 API Changes

Deprecations

Several undocumented functions in `ImageOps` have been deprecated: `gaussian_blur`, `gblur`, `unsharp_mask`, `usm` and `box_blur`. Use the equivalent operations in `ImageFilter` instead. These functions will be removed in a future release.

TIFF Metadata Changes

- TIFF tags with unknown type/quantity now default to being bare values if they are 1 element, where previously they would be a single element tuple. This is only with the new api, not the legacy api. This normalizes the handling of fields, so that the metadata with inferred or image specified counts are handled the same as metadata with count specified in the TIFF spec.
- The `PhotoshopInfo`, `XMP`, and `JPEGTables` tags now have a defined type (bytes) and a count of 1.
- The `ImageJMetaDataByteCounts` tag now has an arbitrary number of items, as there can be multiple items, one for UTF-8, and one for UTF-16.

Core Image API Changes

These are internal functions that should not have been used by user code, but they were accessible from the python layer.

Debugging code within `Image.core.grabclipboard` was removed. It had been marked as will be removed in future versions since PIL. When enabled, it identified the format of the clipboard data.

The `PIL.Image.core.copy` and `PIL.Image.Image.im.copy2` methods have been removed.

The `PIL.Image.core.getcount` methods have been removed, use `PIL.Image.core.get_stats()['new_count']` property instead.

6.16.2 API Additions

Get One Channel From Image

A new method `PIL.Image.Image.getchannel()` has been added to return a single channel by index or name. For example, `image.getchannel("A")` will return alpha channel as separate image. `getchannel` should work up to 6 times faster than `image.split()[0]` in previous Pillow versions.

Box Blur

A new filter, `PIL.ImageFilter.BoxBlur`, has been added. This is a filter with similar results to a Gaussian blur, but is much faster.

Partial Resampling

Added new argument `box` for `PIL.Image.Image.resize()`. This argument defines a source rectangle from within the source image to be resized. This is very similar to the `image.crop(box).resize(size)` sequence except that `box` can be specified with subpixel accuracy.

New Transpose Operation

The `Image.TRANSVERSE` operation has been added to `PIL.Image.Image.transpose()`. This is equivalent to a transpose operation about the opposite diagonal.

Multiband Filters

There is a new `PIL.ImageFilter.MultibandFilter` base class for image filters that can run on all channels of an image in one operation. The original `PIL.ImageFilter.Filter` class remains for image filters that can process only single band images, or require splitting of channels prior to filtering.

6.16.3 Other Changes

Loading 16-bit TIFF Images

Pillow now can read 16-bit multichannel TIFF files including files with alpha transparency. The image data is truncated to 8-bit precision.

Pillow now can read 16-bit signed integer single channel TIFF files. The image data is promoted to 32-bit for storage and processing.

SGI Images

Pillow can now read and write uncompressed 16-bit multichannel SGI images to and from RGB and RGBA formats. The image data is truncated to 8-bit precision.

Pillow can now read RLE encoded SGI images in both 8 and 16-bit precision.

Performance

This release contains several performance improvements:

- Many memory bandwidth-bounded operations such as crop, image allocation, conversion, split into bands and merging from bands are up to 2x faster.
- Upscaling of multichannel images (such as RGB) is accelerated by 5-10%
- JPEG loading is accelerated up to 15% and JPEG saving up to 20% when using a recent version of libjpeg-turbo.
- `Image.transpose` has been accelerated 15% or more by using a cache friendly algorithm.
- ImageFilters based on Kernel convolution are significantly faster due to the new `MultibandFilter` feature.
- All memory allocation for images is now done in blocks, rather than falling back to an allocation for each scan line for images larger than the block size.

CMYK Conversion

The basic CMYK->RGB conversion has been tweaked to match the formula from Google Chrome. This produces an image that is generally lighter than the previous formula, and more in line with what color managed applications produce.

6.17 4.2.1

There are no functional changes in this release.

6.17.1 Fixed Windows PyPy Build

A change in the 4.2.0 cycle broke the Windows PyPy build. This has been fixed, and PyPy is now part of the Windows CI matrix.

6.18 4.2.0

6.18.1 Added Complex Text Rendering

Pillow now supports complex text rendering for scripts requiring glyph composition and bidirectional flow. This optional feature adds three dependencies: `harfbuzz`, `frididi`, and `raqm`. See the [install documentation](#) for further details. This feature is tested and works on Unix and Mac, but has not yet been built on Windows platforms.

6.18.2 New Optional Parameters

- `PIL.ImageDraw.floodfill()` has a new optional parameter: `threshold`. This specifies a tolerance for the color to replace with the flood fill.
- The TIFF and PDF image writers now support the `append_images` optional parameter for specifying additional images to create multipage outputs.

6.18.3 New DecompressionBomb Warning

`PIL.Image.Image.crop()` now may raise a `DecompressionBomb` warning if the crop region enlarges the image over the threshold specified by `PIL.Image.MAX_PIXELS`.

6.18.4 Removed Deprecated Items

Several deprecated items have been removed.

- The methods `PIL.ImageWin.Dib.fromstring()`, `PIL.ImageWin.Dib.tostring()` and `PIL.TiffImagePlugin.ImageFileDirectory_v2.as_dict()` have been removed.
- Before Pillow 4.2.0, attempting to save an RGBA image as JPEG would discard the alpha channel. From Pillow 3.4.0, a deprecation warning was shown. From Pillow 4.2.0, the deprecation warning is removed and an `IOError` is raised.

6.18.5 Removed Core Image Function

The unused function `Image.core.new_array` was removed. This is an internal function that should not have been used by user code, but it was accessible from the python layer.

6.19 4.1.1

6.19.1 Fix Regression with reading DPI from EXIF data

Some JPEG images don't contain DPI information in the image metadata, but do contain it in the EXIF data. A patch was added in 4.1.0 to read from the EXIF data, but it did not accept all possible types that could be included there. This fix adds the ability to read ints as well as rational values.

6.19.2 Incompatibility between 3.6.0 and 3.6.1

CPython 3.6.1 added a new symbol, `PySlice_GetIndicesEx`, which was not present in 3.6.0. This had the effect of causing binaries compiled on CPython 3.6.1 to not work on installations of C-Python 3.6.0. This fix undefines `PySlice_GetIndicesEx` if it exists to restore compatibility with both 3.6.0 and 3.6.1. See <https://bugs.python.org/issue29943> for more details.

6.20 4.1.0

6.20.1 Removed Deprecated Items

Several deprecated items have been removed.

- Support for spaces in tiff kwargs in the parameters for 'x resolution', 'y resolution', 'resolution unit', and 'date time' has been removed. Underscores should be used instead.
- The methods `PIL.ImageDraw.ImageDraw.setink()`, `PIL.ImageDraw.ImageDraw.setfill()`, and `PIL.ImageDraw.ImageDraw.setFont()` have been removed.

6.20.2 Closing Files When Opening Images

The file handling when opening images has been overhauled. Previously, Pillow would attempt to close some, but not all image formats after loading the image data. Now, the following behavior is specified:

- For images where an open file is passed in, it is the responsibility of the calling code to close the file.
- For images where Pillow opens the file and the file is known to have only one frame, the file is closed after loading.
- If the file has more than one frame, or if it can't be determined, then the file is left open to permit seeking to subsequent frames. It will be closed, eventually, in the `close` or `__del__` methods.
- If the image is memory mapped, then we can't close the mapping to the underlying file until we are done with the image. The mapping will be closed in the `close` or `__del__` method.

6.20.3 Changes to GIF Handling When Saving

The `PIL.GifImagePlugin` code has been refactored to fix the flow when saving images. There are two external changes that arise from this:

- An `PIL.ImagePalette.ImagePalette` object is now accepted as a specified palette argument in `PIL.Image.Image.save()`.
- The image to be saved is no longer modified in place by any of the operations of the save function. Previously it was modified when optimizing the image palette.

This refactor fixed some bugs with palette handling when saving multiple frame GIFs.

6.20.4 New Method: `Image.remap_palette`

The method `PIL.Image.Image.remap_palette()` has been added. This method was hoisted from the `GifImagePlugin` code used to optimize the palette.

6.20.5 Added Decoder Registry and Support for Python Based Decoders

There is now a decoder registry similar to the image plugin registries. Image plugins can register a decoder, and it will be called when the decoding is requested. This allows for the creation of pure Python decoders. While the Python decoders will not be as fast as their C based counterparts, they may be easier and quicker to develop or safer to run.

6.20.6 Tests

Many tests have been added, including correctness tests for image formats that have been previously untested.

We are now running automated tests in Docker containers against more Linux versions than are provided on Travis CI, which is currently Ubuntu 14.04 x64. This Pillow release is tested on 64-bit Alpine, Arch, Ubuntu 12.04 and 16.04, and 32-bit Debian Stretch and Ubuntu 14.04. This also covers a wider range of dependency versions than are provided on Travis natively.

6.21 4.0.0

6.21.1 Python 2.6 and 3.2 Dropped

Pillow 4.0 no longer supports Python 2.6 and 3.2. We will not be creating binaries, testing, or retaining compatibility with these releases. This release removes some workarounds for those Python releases, so the final working version of Pillow on 2.6 or 3.2 is 3.4.2.

6.21.2 Support added for Python 3.6

Pillow 4.0 supports Python 3.6.

6.21.3 OleFileIO.py

OleFileIO.py has been removed as a vendored file and is now installed from the upstream olefile pypi package. All internal dependencies are redirected to the olefile package. Direct accesses to `PIL.OlefileIO` raises a deprecation warning, then patches the upstream olefile into `sys.modules` in its place.

6.21.4 SGI image save

It is now possible to save images in modes `L`, `RGB`, and `RGBA` to the uncompressed SGI image format.

6.21.5 Zero sized images

Pillow 3.4.0 removed support for creating images with `(0,0)` size. This has been reenabled, restoring pre 3.4 behavior.

6.21.6 Internal `handles_eof` flag

The `handles_eof` flag for decoding images has been removed, as there were no internal users of the flag. Anyone maintaining image decoders outside of the Pillow source tree should consider using the cleanup function pointers instead.

6.21.7 `Image.core.stretch` removed

The `stretch` function on the core image object has been removed. This used to be for enlarging the image, but has been aliased to `resize` recently.

6.22 3.4.0

6.22.1 New resizing filters

Two new filters available for `Image.resize()` and `Image.thumbnail()` functions: `BOX` and `HAMMING`. `BOX` is the high-performance filter with two times shorter window than `BILINEAR`. It can be used for image reduction 3 and more times and produces a sharper result than `BILINEAR`.

`HAMMING` filter has the same performance as `BILINEAR` filter while providing the image downscaling quality comparable to `BICUBIC`. Both new filters don't show good quality for the image upscaling.

6.22.2 Deprecation Warning when Saving JPEGs

JPEG images cannot contain an alpha channel. Pillow prior to 3.4.0 silently drops the alpha channel. With this release Pillow will now issue a `DeprecationWarning` when attempting to save a RGBA mode image as a JPEG. This will become an error in Pillow 4.2.

6.22.3 New DDS Decoders

Pillow can now decode DXT3 images, as well as the previously supported DXT1 and DXT5 formats. All three formats are now decoded in C code for better performance.

6.22.4 Append images to GIF

Additional frames can now be appended when saving a GIF file, through the `append_images` argument. The new frames are passed in as a list of images, which may have multiple frames themselves.

Note that the `append_images` argument is only used if `save_all` is also in effect, e.g.:

```
im.save(out, save_all=True, append_images=[im1, im2, ...])
```

6.22.5 Save multiple frame TIFF

Multiple frames can now be saved in a TIFF file by using the `save_all` option. e.g.:

```
im.save("filename.tiff", format="TIFF", save_all=True)
```

6.22.6 Image.core.open_ppm removed

The nominally private/debugging function `Image.core.open_ppm` has been removed. If you were using this function, please use `Image.open` instead.

6.23 3.3.2

6.23.1 Integer overflow in Map.c

Pillow prior to 3.3.2 may experience integer overflow errors in `map.c` when reading specially crafted image files. This may lead to memory disclosure or corruption.

Specifically, when parameters from the image are passed into `Image.core.map_buffer`, the size of the image was calculated with `xsize * ysize * bytes_per_pixel`. This will overflow if the result is larger than `SIZE_MAX`. This is possible on a 32-bit system.

Furthermore this `size` value was added to a potentially attacker provided `offset` value and compared to the size of the buffer without checking for overflow or negative values.

These values were then used for creating pointers, at which point Pillow could read the memory and include it in other images. The image was marked readonly, so Pillow would not ordinarily write to that memory without duplicating the image first.

This issue was found by Cris Neckar at Divergent Security.

6.23.2 Sign Extension in Storage.c

Pillow prior to 3.3.2 and PIL 1.1.7 (at least) do not check for negative image sizes in `ImageNew` in `Storage.c`. A negative image size can lead to a smaller allocation than expected, leading to arbitrary writes.

This issue was found by Cris Neckar at Divergent Security.

6.24 3.3.0

6.24.1 Libimagequant support

There is now support for using `libimagequant` as a higher quality quantization option in `Image.quantize()` on Unix-like platforms. This support requires building Pillow from source against `libimagequant`. We cannot distribute binaries due to licensing differences.

6.24.2 New Setup.py options

There are two new options to control the `build_ext` task in `setup.py`:

- `--debug` dumps all of the directories and files that are checked when searching for libraries or headers when building the extensions.
- `--disable-platform-guessing` removes many of the directories that are checked for libraries and headers for build systems or cross compilers that specify that information in via environment variables.

6.24.3 Resizing

Image resampling for 8-bit per channel images was rewritten using only integer computings. This is faster on most platforms and doesn't introduce precision errors on the wide range of scales. With other performance improvements, this makes resampling 60% faster on average.

Color calculation for images in the `LA` mode on semitransparent pixels was fixed.

6.24.4 Rotation

Rotation for angles divisible by 90 degrees now always uses transposition. This greatly improves both quality and performance in this case. Also, the bug with wrong image size calculation when rotating by 90 degrees was fixed.

6.24.5 Image Metadata

The return type for binary data in version 2 Exif and Tiff metadata has been changed from a tuple of integers to bytes. This is a change from the behavior since 3.0.0.

6.25 3.2.0

6.25.1 New DDS and FTEX Image Plugins

The `DdsImagePlugin` reading DXT1 and DXT5 encoded `.dds` images was added. DXT3 images are not currently supported.

The `FtexImagePlugin` reads textures used for 3D objects in Independence War 2: Edge Of Chaos. The plugin reads a single texture per file, in the `.ftc` (compressed) and `.ftu` (uncompressed) formats.

6.25.2 Updates to the `GbrImagePlugin`

The `GbrImagePlugin` (GIMP brush format) has been updated to fix support for version 1 files and add support for version 2 files.

6.25.3 Passthrough Parameters for `ImageDraw.text`

`ImageDraw.multiline_text` and `ImageDraw.multiline_size` take extra spacing parameters above what are used in `ImageDraw.text` and `ImageDraw.size`. These parameters can now be passed into `ImageDraw.text` and `ImageDraw.size` and they will be passed through to the corresponding multiline functions.

6.25.4 `ImageSequence.Iterator` changes

`ImageSequence.Iterator` is now an actual iterator implementing the `Iterator` protocol. It is also now possible to seek to the first image of the file when using direct indexing.

6.26 3.1.2

6.26.1 CVE-2016-3076 – Buffer overflow in `Jpeg2KEncode.c`

Pillow between 2.5.0 and 3.1.1 may overflow a buffer when writing large Jpeg2000 files, allowing for code execution or other memory corruption.

This occurs specifically in the function `j2k_encode_entry`, at the line:

```
state->buffer = malloc (tile_width * tile_height * components * prec / 8);
```

This vulnerability requires a particular value for `height * width` such that `height * width * components * precision` overflows, at which point the `malloc` will be for a smaller value than expected. The buffer that is allocated will be $((\text{height} * \text{width} * \text{components} * \text{precision}) \bmod (2^{31}) / 8)$, where `components` is 1-4 and `precision` is either 8 or 16. Common values would be 4 components at precision 8 for a standard RGBA image.

The unpackers then split an image that is laid out:

```
RGBARBARGBA...
```

into:

```
RRR.
GGG.
BBB.
AAA.
```

If this buffer is smaller than expected, the `jpeg2k` unpacker functions will write outside the allocation and onto the heap, corrupting memory.

This issue was found by Alyssa Besseling at Atlassian.

6.27 3.1.1

6.27.1 CVE-2016-0740 – Buffer overflow in TiffDecode.c

Pillow 3.1.0 and earlier when linked against libtiff $\geq 4.0.0$ on x64 may overflow a buffer when reading a specially crafted tiff file.

Specifically, libtiff $\geq 4.0.0$ changed the return type of `TIFFScanlineSize` from `int32` to machine dependent `int32|64`. If the scanline is sized so that it overflows an `int32`, it may be interpreted as a negative number, which will then pass the size check in `TiffDecode.c` line 236. To do this, the logical scanline size has to be $> 2\text{gb}$, and for the test file, the allocated buffer size is 64k against a roughly 4gb scan line size. Any image data over 64k is written over the heap, causing a segfault.

This issue was found by security researcher FourOne.

6.27.2 CVE-2016-0775 – Buffer overflow in FliDecode.c

In all versions of Pillow, dating back at least to the last PIL 1.1.7 release, `FliDecode.c` has a buffer overflow error.

Around line 192:

```
case 16:
    /* COPY chunk */
    for (y = 0; y < state->ysize; y++) {
        UINT8* buf = (UINT8*) im->image[y];
        memcpy(buf+x, data, state->xsize);
        data += state->xsize;
    }
    break;
```

The `memcpy` has error where `x` is added to the target buffer address. `x` is used in several internal temporary variable roles, but can take a value up to the width of the image. `im->image[y]` is a set of row pointers to segments of memory that are the size of the row. At the max `y`, this will write the contents of the line off the end of the memory buffer, causing a segfault.

This issue was found by Alyssa Besseling at Atlassian

6.27.3 CVE-2016-2533 – Buffer overflow in PcdDecode.c

In all versions of Pillow, dating back at least to the last PIL 1.1.7 release, `PcdDecode.c` has a buffer overflow error.

The `state.buffer` for `PcdDecode.c` is allocated based on a 3 bytes per pixel sizing, where `PcdDecode.c` wrote into the buffer assuming 4 bytes per pixel. This writes 768 bytes beyond the end of the buffer into other Python object storage. In some cases, this causes a segfault, in others an internal Python malloc error.

6.27.4 Integer overflow in Resample.c

If a large value was passed into the new size for an image, it is possible to overflow an `int32` value passed into `malloc`.

```
kk = malloc(xsize * kmax * sizeof(float)); ... xbounds = malloc(xsize * 2 * sizeof(int));
```

`xsize` is trusted user input. These multiplications can overflow, leading the `malloc`'d buffer to be undersized. These allocations are followed by a loop that writes out of bounds. This can lead to corruption on the heap of the Python process with attacker controlled float data.

This issue was found by Ned Williamson.

6.28 3.1.0

6.28.1 ImageDraw arc, chord and pieslice can now use floats

There is no longer a need to ensure that the start and end arguments for `arc`, `chord` and `pieslice` are integers.

Note that these numbers are not simply rounded internally, but are actually utilised in the drawing process.

6.28.2 Consistent multiline text spacing

When using the `ImageDraw` multiline methods, the spacing between lines was inconsistent, based on the combination on ascenders and descenders.

This has now been fixed, so that lines are offset by their baselines, not the absolute height of each line.

There is also now a default spacing of 4px between lines.

6.28.3 Exif, Jpeg and Tiff Metadata

There were major changes in the TIFF `ImageFileDirectory` support in Pillow 3.0 that led to a number of regressions. Some of them have been fixed in Pillow 3.1, and some of them have been extended to have different behavior.

TiffImagePlugin.IFDRational

Pillow 3.0 changed rational metadata to use a float. In Pillow 3.1, this has changed to allow the expression of 0/0 as a valid piece of rational metadata to reflect usage in the wild.

Rational metadata is now encapsulated in an `IFDRational` instance. This class extends the `Rational` class to allow a denominator of 0. It compares as a float or a number, but does allow access to the raw numerator and denominator values through attributes.

When used in a `ImageFileDirectory_v1`, a 2 item tuple is returned of the numerator and denominator, as was done previously.

This class should be used when adding a rational value to an `ImageFileDirectory` for saving to image metadata.

JpegImagePlugin._getexif

In Pillow 3.0, the dictionary returned from the private, experimental, but generally widely used `_getexif` function changed to reflect the `ImageFileDirectory_v2` format, without a fallback to the previous format.

In Pillow 3.1, `_getexif` now returns a dictionary compatible with Pillow 2.9 and earlier, built with `ImageFileDirectory_v1` instances. Additionally, any single item tuples have been unwrapped and return a bare element.

The format returned by Pillow 3.0 has been abandoned. A more fully featured interface for EXIF is anticipated in a future release.

Out of Spec Metadata

In Pillow 3.0 and 3.1, images that contain metadata that is internally consistent, but not in agreement with the TIFF spec, may cause an exception when reading the metadata. This can happen when a tag that is specified to have a single value is stored with an array of values.

It is anticipated that this behavior will change in future releases.

6.29 3.0.0

6.29.1 Saving Multipage Images

There is now support for saving multipage images in the GIF and PDF formats. To enable this functionality, pass in `save_all=True` as a keyword argument to the save:

```
im.save('test.pdf', save_all=True)
```

6.29.2 Tiff ImageFileDirectory Rewrite

The Tiff ImageFileDirectory metadata code has been rewritten. Where previously it returned a somewhat arbitrary set of values and tuples, it now returns bare values where appropriate and tuples when the metadata item is a sequence or collection.

The original metadata is still available in the `TiffImage.tags`, the new values are available in the `TiffImage.tags_v2` member. The old structures will be deprecated at some point in the future. When saving Tiff metadata, new code should use the `TiffImagePlugin.ImageFileDirectory_v2` class.

6.29.3 Deprecated Methods

Several methods that have been marked as deprecated for many releases have been removed in this release:

```
Image.tostring()
Image.fromstring()
Image.offset()
ImageDraw.setink()
ImageDraw.setfill()
The ImageFileIO module
The ImageFont.FreeTypeFont and ImageFont.truetype ``file`` keyword arg
The ImagePalette private _make functions
ImageWin.fromstring()
ImageWin.tostring()
```

6.29.4 LibJpeg and Zlib are Required by Default

The external dependencies on libjpeg and zlib are now required by default. If the headers or libraries are not found, then installation will abort with an error. This behaviour can be disabled with the `--disable-libjpeg` and `--disable-zlib` flags.

6.30 2.8.0

6.30.1 Open HTTP response objects with Image.open

HTTP response objects returned from `urllib2.urlopen(url)` or `requests.get(url, stream=True).raw` are ‘file-like’ but do not support `.seek()` operations. As a result PIL was unable to open them as images, requiring a wrap in `cStringIO` or `BytesIO`.

Now new functionality has been added to `Image.open()` by way of an `.seek(0)` check and catch on exception `AttributeError` or `io.UnsupportedOperation`. If this is caught we attempt to wrap the object using `io.BytesIO` (which will only work on buffer-file-like objects).

This allows opening of files using both `urllib2` and `requests`, e.g.:

```
Image.open(urllib2.urlopen(url))
Image.open(requests.get(url, stream=True).raw)
```

If the response uses content-encoding (compression, either `gzip` or `deflate`) then this will fail as both the `urllib2` and `requests` raw file object will produce compressed data in that case. Using Content-Encoding on images is rather non-sensical as most images are already compressed, but it can still happen.

For `requests` the work-around is to set the `decode_content` attribute on the raw object to `True`:

```
response = requests.get(url, stream=True)
response.raw.decode_content = True
image = Image.open(response.raw)
```

6.31 2.7.0

6.31.1 Sane Plugin

The Sane plugin has now been split into its own repo: <https://github.com/python-pillow/Sane>.

6.31.2 Png text chunk size limits

To prevent potential denial of service attacks using compressed text chunks, there are now limits to the decompressed size of text chunks decoded from PNG images. If the limits are exceeded when opening a PNG image a `ValueError` will be raised.

Individual text chunks are limited to `PIL.PngImagePlugin.MAX_TEXT_CHUNK`, set to 1MB by default. The total decompressed size of all text chunks is limited to `PIL.PngImagePlugin.MAX_TEXT_MEMORY`, which defaults to 64MB. These values can be changed prior to opening PNG images if you know that there are large text blocks that are desired.

6.31.3 Image resizing filters

Image resizing methods `resize()` and `thumbnail()` take a `resample` argument, which tells which filter should be used for resampling. Possible values are: `PIL.Image.NEAREST`, `PIL.Image.BILINEAR`, `PIL.Image.BICUBIC` and `PIL.Image.ANTIALIAS`. Almost all of them were changed in this version.

Bicubic and bilinear downscaling

From the beginning `BILINEAR` and `BICUBIC` filters were based on affine transformations and used a fixed number of pixels from the source image for every destination pixel (2x2 pixels for `BILINEAR` and 4x4 for `BICUBIC`). This gave an unsatisfactory result for downscaling. At the same time, a high quality convolutions-based algorithm with flexible kernel was used for `ANTIALIAS` filter.

Starting from Pillow 2.7.0, a high quality convolutions-based algorithm is used for all of these three filters.

If you have previously used any tricks to maintain quality when downscaling with `BILINEAR` and `BICUBIC` filters (for example, reducing within several steps), they are unnecessary now.

Antialias renamed to Lanczos

A new `PIL.Image.LANCZOS` constant was added instead of `ANTIALIAS`.

When `ANTIALIAS` was initially added, it was the only high-quality filter based on convolutions. It's name was supposed to reflect this. Starting from Pillow 2.7.0 all resize method are based on convolutions. All of them are antialias from now on. And the real name of the `ANTIALIAS` filter is Lanczos filter.

The `ANTIALIAS` constant is left for backward compatibility and is an alias for `LANCZOS`.

Lanczos upscaling quality

The image upscaling quality with `LANCZOS` filter was almost the same as `BILINEAR` due to bug. This has been fixed.

Bicubic upscaling quality

The `BICUBIC` filter for affine transformations produced sharp, slightly pixelated image for upscaling. Bicubic for convolutions is more soft.

Resize performance

In most cases, convolution is more a expensive algorithm for downscaling because it takes into account all the pixels of source image. Therefore `BILINEAR` and `BICUBIC` filters' performance can be lower than before. On the other hand the quality of `BILINEAR` and `BICUBIC` was close to `NEAREST`. So if such quality is suitable for your tasks you can switch to `NEAREST` filter for downscaling, which will give a huge improvement in performance.

At the same time performance of convolution resampling for downscaling has been improved by around a factor of two compared to the previous version. The upscaling performance of the `LANCZOS` filter has remained the same. For `BILINEAR` filter it has improved by 1.5 times and for `BICUBIC` by four times.

Default filter for thumbnails

In Pillow 2.5 the default filter for `thumbnail()` was changed from `NEAREST` to `ANTIALIAS`. Antialias was chosen because all the other filters gave poor quality for reduction. Starting from Pillow 2.7.0, `ANTIALIAS` has been replaced with `BICUBIC`, because it's faster and `ANTIALIAS` doesn't give any advantages after downscaling with libjpeg, which uses supersampling internally, not convolutions.

6.31.4 Image transposition

A new method `PIL.Image.TRANSPOSE` has been added for the `transpose()` operation in addition to `FLIP_LEFT_RIGHT`, `FLIP_TOP_BOTTOM`, `ROTATE_90`, `ROTATE_180`, `ROTATE_270`. `TRANSPOSE` is an algebra transpose, with an image reflected across its main diagonal.

The speed of `ROTATE_90`, `ROTATE_270` and `TRANSPOSE` has been significantly improved for large images which don't fit in the processor cache.

6.31.5 Gaussian blur and unsharp mask

The `GaussianBlur()` implementation has been replaced with a sequential application of box filters. The new implementation is based on "Theoretical foundations of Gaussian convolution by extended box filtering" from the Mathematical Image Analysis Group. As `UnsharpMask()` implementations use Gaussian blur internally, all changes from this chapter are also applicable to it.

Blur radius

There was an error in the previous version of Pillow, where blur radius (the standard deviation of Gaussian) actually meant blur diameter. For example, to blur an image with actual radius 5 you were forced to use value 10. This has been fixed. Now the meaning of the radius is the same as in other software.

If you used a Gaussian blur with some radius value, you need to divide this value by two.

Blur performance

Box filter computation time is constant relative to the radius and depends on source image size only. Because the new Gaussian blur implementation is based on box filter, its computation time also doesn't depend on the blur radius.

For example, previously, if the execution time for a given test image was 1 second for radius 1, 3.6 seconds for radius 10 and 17 seconds for 50, now blur with any radius on same image is executed for 0.2 seconds.

Blur quality

The previous implementation takes into account only source pixels within $2 * \text{standard deviation radius}$ for every destination pixel. This was not enough, so the quality was worse compared to other Gaussian blur software.

The new implementation does not have this drawback.

6.31.6 TIFF Parameter Changes

Several kwarg parameters for saving TIFF images were previously specified as strings with included spaces (e.g. 'x resolution'). This was difficult to use as kwargs without constructing and passing a dictionary. These parameters now use the underscore character instead of space. (e.g. 'x_resolution')

Deprecations and removals

This page lists Pillow features that are deprecated, or have been removed in past major releases, and gives the alternatives to use instead.

7.1 Deprecated features

Below are features which are considered deprecated. Where appropriate, a `DeprecationWarning` is issued.

7.1.1 `PILLOW_VERSION` constant

Deprecated since version 5.2.0.

`PILLOW_VERSION` has been deprecated and will be removed in a future release. Use `__version__` instead.

It was initially removed in Pillow 7.0.0, but brought back in 7.1.0 to give projects more time to upgrade.

7.1.2 `ImageCms.CmsProfile` attributes

Deprecated since version 3.2.0.

Some attributes in `ImageCms.CmsProfile` are deprecated. From 6.0.0, they issue a `DeprecationWarning`:

Deprecated	Use instead
<code>color_space</code>	<code>Padded xcolor_space</code>
<code>pcs</code>	<code>Padded connection_space</code>
<code>product_copyright</code>	<code>Unicode copyright</code>
<code>product_desc</code>	<code>Unicode profile_description</code>
<code>product_description</code>	<code>Unicode profile_description</code>
<code>product_manufacturer</code>	<code>Unicode manufacturer</code>
<code>product_model</code>	<code>Unicode model</code>

7.2 Removed features

Deprecated features are only removed in major releases after an appropriate period of deprecation has passed.

7.2.1 Python 2.7

Removed in version 7.0.0.

Python 2.7 reached end-of-life on 2020-01-01. Pillow 6.x was the last series to support Python 2.

7.2.2 Image.__del__

Removed in version 7.0.0.

Implicitly closing the image's underlying file in `Image.__del__` has been removed. Use a context manager or call `Image.close()` instead to close the file in a deterministic way.

Previous method:

```
im = Image.open("hopper.png")
im.save("out.jpg")
```

Use instead:

```
with Image.open("hopper.png") as im:
    im.save("out.jpg")
```

7.2.3 PIL.*ImagePlugin.__version__ attributes

Removed in version 7.0.0.

The version constants of individual plugins have been removed. Use `PIL.__version__` instead.

Removed	Removed	Removed
BmpImagePlugin. __version__	Jpeg2KImagePlugin. __version__	PngImagePlugin. __version__
CurImagePlugin. __version__	JpegImagePlugin. __version__	PpmImagePlugin. __version__
DcxImagePlugin. __version__	McIdasImagePlugin. __version__	PsdImagePlugin. __version__
EpsImagePlugin. __version__	MicImagePlugin. __version__	SgiImagePlugin. __version__
FliImagePlugin. __version__	MpegImagePlugin. __version__	SunImagePlugin. __version__
FpxImagePlugin. __version__	MpoImagePlugin. __version__	TgaImagePlugin. __version__
GdImageFile. __version__	MspImagePlugin. __version__	TiffImagePlugin. __version__
GifImagePlugin. __version__	PalmImagePlugin. __version__	WmfImagePlugin. __version__
IcoImagePlugin. __version__	PcdImagePlugin. __version__	XbmImagePlugin. __version__
ImImagePlugin. __version__	PcxImagePlugin. __version__	XpmImagePlugin. __version__
ImtImagePlugin. __version__	PdfImagePlugin. __version__	XVThumbImagePlugin. __version__
IptcImagePlugin. __version__	PixarImagePlugin. __version__	

7.2.4 PyQt4 and PySide

Removed in version 7.0.0.

Qt 4 reached end-of-life on 2015-12-19. Its Python bindings are also EOL: PyQt4 since 2018-08-31 and PySide since 2015-10-14.

Support for PyQt4 and PySide has been removed from `ImageQt`. Please upgrade to PyQt5 or PySide2.

7.2.5 Setting the size of TIFF images

Removed in version 7.0.0.

Setting the size of a TIFF image directly (eg. `im.size = (256, 256)`) throws an error. Use `Image.resize` instead.

7.2.6 VERSION constant

Removed in version 6.0.0.

`VERSION` (the old PIL version, always 1.1.7) has been removed. Use `__version__` instead.

7.2.7 Undocumented ImageOps functions

Removed in version 6.0.0.

Several undocumented functions in `ImageOps` have been removed. Use the equivalents in `ImageFilter` instead:

Removed	Use instead
<code>ImageOps.box_blur</code>	<code>ImageFilter.BoxBlur</code>
<code>ImageOps.gaussian_blur</code>	<code>ImageFilter.GaussianBlur</code>
<code>ImageOps.gblur</code>	<code>ImageFilter.GaussianBlur</code>
<code>ImageOps.usm</code>	<code>ImageFilter.UnsharpMask</code>
<code>ImageOps.unsharp_mask</code>	<code>ImageFilter.UnsharpMask</code>

7.2.8 PIL.OleFileIO

Removed in version 6.0.0.

`PIL.OleFileIO` was removed as a vendored file and in Pillow 4.0.0 (2017-01) in favour of the upstream `olefile` Python package, and replaced with an `ImportError` in 5.0.0 (2018-01). The deprecated file has now been removed from Pillow. If needed, install from PyPI (eg. `python3 -m pip install olefile`).

CHAPTER 8

Indices and tables

- `genindex`
- `modindex`
- `search`

p

PIL._binary, 123
PIL.BdfFontFile, 116
PIL.BmpImagePlugin, 124
PIL.BufrStubImagePlugin, 125
PIL.ContainerIO, 116
PIL.CurImagePlugin, 125
PIL.DcxImagePlugin, 125
PIL.EpsImagePlugin, 126
PIL.ExifTags, 112
PIL.FitsStubImagePlugin, 126
PIL.FliImagePlugin, 126
PIL.FontFile, 117
PIL.FpxImagePlugin, 127
PIL.GbrImagePlugin, 127
PIL.GdImageFile, 117
PIL.GifImagePlugin, 127
PIL.GimpGradientFile, 118
PIL.GimpPaletteFile, 118
PIL.GribStubImagePlugin, 128
PIL.Hdf5StubImagePlugin, 129
PIL.IcnsImagePlugin, 129
PIL.IcoImagePlugin, 130
PIL.Image, 47
PIL.ImageChops, 63
PIL.ImageCms, 67
PIL.ImageColor, 66
PIL.ImageDraw, 81
PIL.ImageDraw2, 118
PIL.ImageEnhance, 88
PIL.ImageFile, 89
PIL.ImageFilter, 91
PIL.ImageFont, 93
PIL.ImageGrab, 99
PIL.ImageMath, 100
PIL.ImageMorph, 101
PIL.ImageOps, 103
PIL.ImagePalette, 106
PIL.ImagePath, 107
PIL.ImageQt, 108
PIL.ImageSequence, 108
PIL.ImageShow, 119
PIL.ImageStat, 109
PIL.ImageTk, 110
PIL.ImageTransform, 120
PIL.ImageWin, 111
PIL.ImImagePlugin, 130
PIL.ImtImagePlugin, 131
PIL.IptcImagePlugin, 131
PIL.Jpeg2KImagePlugin, 132
PIL.JpegImagePlugin, 131
PIL.JpegPresets, 121
PIL.McIdasImagePlugin, 133
PIL.MicImagePlugin, 133
PIL.MpegImagePlugin, 133
PIL.MspImagePlugin, 133
PIL.PaletteFile, 122
PIL.PalmImagePlugin, 134
PIL.PcdImagePlugin, 134
PIL.PcfFontFile, 122
PIL.PcxImagePlugin, 134
PIL.PdfImagePlugin, 134
PIL.PixarImagePlugin, 134
PIL.PngImagePlugin, 134
PIL.PpmImagePlugin, 136
PIL.PsdImagePlugin, 136
PIL.PSDraw, 113
PIL.PyAccess, 115
PIL.SgiImagePlugin, 137
PIL.SpiderImagePlugin, 137
PIL.SunImagePlugin, 138
PIL.TarIO, 123
PIL.TgaImagePlugin, 138
PIL.TiffImagePlugin, 138
PIL.TiffTags, 112
PIL.WalImageFile, 123
PIL.WebPImagePlugin, 141
PIL.WmfImagePlugin, 142
PIL.XbmImagePlugin, 142

[PIL.XpmImagePlugin](#), 142

[PIL.XVThumbImagePlugin](#), 142

Symbols

`__init__()` (*PIL.TiffTags.TagInfo method*), 113
`__new__()` (*PIL.PngImagePlugin.iTXXt method*), 122

A

`abs()` (*built-in function*), 101
`add()` (*in module PIL.ImageChops*), 64
`add()` (*PIL.PngImagePlugin.PngInfo method*), 122
`add_itxt()` (*PIL.PngImagePlugin.PngInfo method*), 123
`add_modulo()` (*in module PIL.ImageChops*), 64
`add_text()` (*PIL.PngImagePlugin.PngInfo method*), 123
AffineTransform (*class in PIL.ImageTransform*), 120
`alpha_composite()` (*in module PIL.Image*), 48
`alpha_composite()` (*PIL.Image.Image method*), 52
`APP()` (*in module PIL.JpegImagePlugin*), 131
AppendingTiffWriter (*class in PIL.TiffImagePlugin*), 138
`arc()` (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw method*), 83
`arc()` (*PIL.ImageDraw2.Draw method*), 118
`attributes` (*PIL.ImageCms.CmsProfile attribute*), 77
`autocontrast()` (*in module PIL.ImageOps*), 103

B

`bdf_char()` (*in module PIL.BdfFontFile*), 116
BdfFontFile (*class in PIL.BdfFontFile*), 116
`begin_document()` (*PIL.PSDraw.PSDraw method*), 114
`bestsize()` (*PIL.IcnsImagePlugin.IcnsFile method*), 129
`BITFIELDS` (*PIL.BmpImagePlugin.BmpImageFile attribute*), 124
`bitmap` (*PIL.FontFile.FontFile attribute*), 117
`bitmap()` (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw method*), 83
BitmapImage (*class in PIL.ImageTk*), 110

BitStream (*class in PIL.MpegImagePlugin*), 133
`blend()` (*in module PIL.Image*), 48
`blend()` (*in module PIL.ImageChops*), 64
`blue_colorant` (*PIL.ImageCms.CmsProfile attribute*), 78
`blue_primary` (*PIL.ImageCms.CmsProfile attribute*), 79
BmpImageFile (*class in PIL.BmpImagePlugin*), 124
BoxBlur (*class in PIL.ImageFilter*), 92
Brush (*class in PIL.ImageDraw2*), 118
BufrStubImageFile (*class in PIL.BufrStubImagePlugin*), 125
`build_prototype_image()` (*in module PIL.PalmImagePlugin*), 134

C

`call()` (*PIL.PngImagePlugin.ChunkStream method*), 134
`check_text_memory()` (*PIL.PngImagePlugin.PngStream method*), 135
`chord()` (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw method*), 83
`chord()` (*PIL.ImageDraw2.Draw method*), 118
`chromatic_adaption` (*PIL.ImageCms.CmsProfile attribute*), 78
`chromaticity` (*PIL.ImageCms.CmsProfile attribute*), 78
`chunk_acTL()` (*PIL.PngImagePlugin.PngStream method*), 136
`chunk_cHRM()` (*PIL.PngImagePlugin.PngStream method*), 136
`chunk_eXIf()` (*PIL.PngImagePlugin.PngStream method*), 136
`chunk_fcTL()` (*PIL.PngImagePlugin.PngStream method*), 136
`chunk_fdAT()` (*PIL.PngImagePlugin.PngStream method*), 136
`chunk_gAMA()` (*PIL.PngImagePlugin.PngStream method*), 136

- `chunk_iCCP()` (*PIL.PngImagePlugin.PngStream method*), 136
 - `chunk_IDAT()` (*PIL.PngImagePlugin.PngStream method*), 135
 - `chunk_IEND()` (*PIL.PngImagePlugin.PngStream method*), 135
 - `chunk_IHDR()` (*PIL.PngImagePlugin.PngStream method*), 135
 - `chunk_iTXt()` (*PIL.PngImagePlugin.PngStream method*), 136
 - `chunk_pHYs()` (*PIL.PngImagePlugin.PngStream method*), 136
 - `chunk_PLTE()` (*PIL.PngImagePlugin.PngStream method*), 135
 - `chunk_sRGB()` (*PIL.PngImagePlugin.PngStream method*), 136
 - `chunk_tEXt()` (*PIL.PngImagePlugin.PngStream method*), 136
 - `chunk_tRNS()` (*PIL.PngImagePlugin.PngStream method*), 136
 - `chunk_zTXt()` (*PIL.PngImagePlugin.PngStream method*), 136
 - `ChunkStream` (*class in PIL.PngImagePlugin*), 134
 - `cleanup()` (*PIL.ImageFile.PyDecoder method*), 90
 - `close()` (*PIL.Image.Image method*), 62
 - `close()` (*PIL.ImageFile.Parser method*), 90
 - `close()` (*PIL.PngImagePlugin.ChunkStream method*), 135
 - `close()` (*PIL.TarIO.TarIO method*), 123
 - `close()` (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 138
 - `clut` (*PIL.ImageCms.CmsProfile attribute*), 79
 - `CmsProfile` (*class in PIL.ImageCms*), 76
 - `Color3DLUT` (*class in PIL.ImageFilter*), 91
 - `color_space` (*PIL.ImageCms.CmsProfile attribute*), 80
 - `colorant_table` (*PIL.ImageCms.CmsProfile attribute*), 78
 - `colorant_table_out` (*PIL.ImageCms.CmsProfile attribute*), 78
 - `colorimetric_intent` (*PIL.ImageCms.CmsProfile attribute*), 78
 - `colorize()` (*in module PIL.ImageOps*), 103
 - `COM()` (*in module PIL.JpegImagePlugin*), 131
 - `compact()` (*PIL.ImagePath.PIL.ImagePath.Path method*), 108
 - `compile()` (*PIL.FontFile.FontFile method*), 117
 - `composite()` (*in module PIL.Image*), 49
 - `composite()` (*in module PIL.ImageChops*), 64
 - `COMPRESSIONS` (*PIL.BmpImagePlugin.BmpImageFile attribute*), 124
 - `connection_space` (*PIL.ImageCms.CmsProfile attribute*), 76
 - `constant()` (*in module PIL.ImageChops*), 64
 - `ContainerIO` (*class in PIL.ContainerIO*), 116
 - `convert()` (*built-in function*), 101
 - `convert()` (*PIL.Image.Image method*), 52
 - `convert2byte()` (*PIL.SpiderImagePlugin.SpiderImageFile method*), 137
 - `convert_dict_qtables()` (*in module PIL.JpegImagePlugin*), 132
 - `copy()` (*PIL.Image.Image method*), 53
 - `copyright` (*PIL.ImageCms.CmsProfile attribute*), 77
 - `count` (*PIL.ImageStat.PIL.ImageStat.Stat attribute*), 109
 - `crc()` (*PIL.PngImagePlugin.ChunkStream method*), 135
 - `crc_skip()` (*PIL.PngImagePlugin.ChunkStream method*), 135
 - `creation_date` (*PIL.ImageCms.CmsProfile attribute*), 76
 - `crop()` (*in module PIL.ImageOps*), 104
 - `crop()` (*PIL.Image.Image method*), 53
 - `CurImageFile` (*class in PIL.CurImagePlugin*), 125
 - `curved()` (*in module PIL.GimpGradientFile*), 118
 - `cvt_enum()` (*PIL.TiffTags.TagInfo method*), 113
- ## D
- `darker()` (*in module PIL.ImageChops*), 64
 - `data()` (*PIL.GifImagePlugin.GifImageFile method*), 127
 - `dataforsize()` (*PIL.IcnsImagePlugin.IcnsFile method*), 129
 - `DcxImageFile` (*class in PIL.DcxImagePlugin*), 125
 - `decode()` (*PIL.ImageFile.PyDecoder method*), 90
 - `decode()` (*PIL.MspImagePlugin.MspDecoder method*), 133
 - `decode()` (*PIL.SgiImagePlugin.SGI16Decoder method*), 137
 - `deform()` (*in module PIL.ImageOps*), 104
 - `denominator` (*PIL.TiffImagePlugin.IFDRational attribute*), 139
 - `device_class` (*PIL.ImageCms.CmsProfile attribute*), 76
 - `Dib` (*class in PIL.ImageWin*), 111
 - `DibImageFile` (*class in PIL.BmpImagePlugin*), 125
 - `difference()` (*in module PIL.ImageChops*), 64
 - `DisplayViewer` (*class in PIL.ImageShow*), 119
 - `DQT()` (*in module PIL.JpegImagePlugin*), 131
 - `draft()` (*PIL.Image.Image method*), 54
 - `draft()` (*PIL.JpegImagePlugin.JpegImageFile method*), 131
 - `Draw` (*class in PIL.ImageDraw2*), 118
 - `draw()` (*PIL.ImageWin.Dib method*), 111
 - `dump()` (*in module PIL.IptcImagePlugin*), 131
 - `duplicate()` (*in module PIL.ImageChops*), 64

E

`ellipse()` (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw* method), 83

`ellipse()` (*PIL.ImageDraw2.Draw* method), 118

`end_document()` (*PIL.PSDraw.PSDraw* method), 114

`EogViewer` (class in *PIL.ImageShow*), 119

`EpsImageFile` (class in *PIL.EpsImagePlugin*), 126

`equalize()` (in module *PIL.ImageOps*), 105

`eval()` (in module *PIL.Image*), 49

`eval()` (in module *PIL.ImageMath*), 100

`exif_transpose()` (in module *PIL.ImageOps*), 106

`expand()` (in module *PIL.ImageOps*), 105

`expose()` (*PIL.ImageWin.Dib* method), 111

`ExtentTransform` (class in *PIL.ImageTransform*), 120

`extrema` (*PIL.ImageStat.PIL.ImageStat.Stat* attribute), 109

F

`feed()` (*PIL.ImageFile.Parser* method), 90

`field()` (*PIL.IptcImagePlugin.IptcImageFile* method), 131

`fieldSizes` (*PIL.TiffImagePlugin.AppendingTiffWriter* attribute), 138

`filename` (in module *PIL.Image*), 62

`filter()` (*PIL.Image.Image* method), 54

`finalize()` (*PIL.TiffImagePlugin.AppendingTiffWriter* method), 138

`fit()` (in module *PIL.ImageOps*), 105

`FITSStubImageFile` (class in *PIL.FitsStubImagePlugin*), 126

`fixIFD()` (*PIL.TiffImagePlugin.AppendingTiffWriter* method), 138

`fixOffsets()` (*PIL.TiffImagePlugin.AppendingTiffWriter* method), 138

`FliImageFile` (class in *PIL.FliImagePlugin*), 126

`flip()` (in module *PIL.ImageOps*), 105

`float()` (built-in function), 101

`floodfill()` (*PIL.ImageDraw.PIL.ImageDraw* method), 88

`flush()` (*PIL.ImageDraw2.Draw* method), 118

`Font` (class in *PIL.ImageDraw2*), 118

`font_variant()` (*PIL.ImageFont.FreeTypeFont* method), 96

`FontFile` (class in *PIL.FontFile*), 117

`format` (in module *PIL.Image*), 63

`format` (*PIL.BmpImagePlugin.BmpImageFile* attribute), 125

`format` (*PIL.BmpImagePlugin.DibImageFile* attribute), 125

`format` (*PIL.BufrStubImagePlugin.BufrStubImageFile* attribute), 125

`format` (*PIL.CurImagePlugin.CurImageFile* attribute), 125

`format` (*PIL.DcxImagePlugin.DcxImageFile* attribute), 125

`format` (*PIL.EpsImagePlugin.EpsImageFile* attribute), 126

`format` (*PIL.FitsStubImagePlugin.FITSStubImageFile* attribute), 126

`format` (*PIL.FliImagePlugin.FliImageFile* attribute), 126

`format` (*PIL.FpxImagePlugin.FpxImageFile* attribute), 127

`format` (*PIL.GbrImagePlugin.GbrImageFile* attribute), 127

`format` (*PIL.GdImageFile.GdImageFile* attribute), 117

`format` (*PIL.GifImagePlugin.GifImageFile* attribute), 127

`format` (*PIL.GribStubImagePlugin.GribStubImageFile* attribute), 128

`format` (*PIL.Hdf5StubImagePlugin.HDF5StubImageFile* attribute), 129

`format` (*PIL.IcnsImagePlugin.IcnsImageFile* attribute), 129

`format` (*PIL.IcoImagePlugin.IcoImageFile* attribute), 130

`format` (*PIL.ImageShow.UnixViewer* attribute), 119

`format` (*PIL.ImageShow.Viewer* attribute), 119

`format` (*PIL.ImImagePlugin.ImImageFile* attribute), 130

`format` (*PIL.ImtImagePlugin.ImtImageFile* attribute), 131

`format` (*PIL.IptcImagePlugin.IptcImageFile* attribute), 131

`format` (*PIL.Jpeg2KImagePlugin.Jpeg2KImageFile* attribute), 132

`format` (*PIL.JpegImagePlugin.JpegImageFile* attribute), 132

`format` (*PIL.McIdasImagePlugin.McIdasImageFile* attribute), 133

`format` (*PIL.MicImagePlugin.MicImageFile* attribute), 133

`format` (*PIL.MpegImagePlugin.MpegImageFile* attribute), 133

`format` (*PIL.MspImagePlugin.MspImageFile* attribute), 134

`format` (*PIL.PcdImagePlugin.PcdImageFile* attribute), 134

`format` (*PIL.PcxImagePlugin.PcxImageFile* attribute), 134

`format` (*PIL.PixarImagePlugin.PixarImageFile* attribute), 134

`format` (*PIL.PngImagePlugin.PngImageFile* attribute), 135

`format` (*PIL.PpmImagePlugin.PpmImageFile* at-

tribute), 136
format (PIL.PsdImagePlugin.PsdImageFile attribute), 136
format (PIL.SgiImagePlugin.SgiImageFile attribute), 137
format (PIL.SpiderImagePlugin.SpiderImageFile attribute), 137
format (PIL.SunImagePlugin.SunImageFile attribute), 138
format (PIL.TgaImagePlugin.TgaImageFile attribute), 138
format (PIL.TiffImagePlugin.TiffImageFile attribute), 141
format (PIL.WebPImagePlugin.WebPImageFile attribute), 141
format (PIL.WmfImagePlugin.WmfStubImageFile attribute), 142
format (PIL.XbmImagePlugin.XbmImageFile attribute), 142
format (PIL.XpmImagePlugin.XpmImageFile attribute), 142
format (PIL.XVThumbImagePlugin.XVThumbImageFile attribute), 142
format_description (PIL.BmpImagePlugin.BmpImageFile attribute), 125
format_description (PIL.BmpImagePlugin.DibImageFile attribute), 125
format_description (PIL.BufrStubImagePlugin.BufrStubImageFile attribute), 125
format_description (PIL.CurImagePlugin.CurImageFile attribute), 125
format_description (PIL.DcxImagePlugin.DcxImageFile attribute), 125
format_description (PIL.EpsImagePlugin.EpsImageFile attribute), 126
format_description (PIL.FitsStubImagePlugin.FITSSStubImageFile attribute), 126
format_description (PIL.FliImagePlugin.FliImageFile attribute), 126
format_description (PIL.FpxImagePlugin.FpxImageFile attribute), 127
format_description (PIL.GbrImagePlugin.GbrImageFile attribute), 127
format_description (PIL.GdImageFile.GdImageFile attribute), 117
format_description (PIL.GifImagePlugin.GifImageFile attribute), 127
format_description (PIL.GribStubImagePlugin.GribStubImageFile attribute), 128
format_description (PIL.Hdf5StubImagePlugin.HDF5StubImageFile attribute), 129
format_description (PIL.IcnsImagePlugin.IcnsImageFile attribute), 129
format_description (PIL.IcoImagePlugin.IcoImageFile attribute), 130
format_description (PIL.ImImagePlugin.ImImageFile attribute), 130
format_description (PIL.ImtImagePlugin.ImtImageFile attribute), 131
format_description (PIL.IptcImagePlugin.IptcImageFile attribute), 131
format_description (PIL.Jpeg2KImagePlugin.Jpeg2KImageFile attribute), 132
format_description (PIL.JpegImagePlugin.JpegImageFile attribute), 132
format_description (PIL.McIdasImagePlugin.McIdasImageFile attribute), 133
format_description (PIL.MicImagePlugin.MicImageFile attribute), 133
format_description (PIL.MpegImagePlugin.MpegImageFile attribute), 133
format_description (PIL.MspImagePlugin.MspImageFile attribute), 134
format_description (PIL.PcdImagePlugin.PcdImageFile attribute), 134
format_description (PIL.PcxImagePlugin.PcxImageFile attribute), 134
format_description (PIL.PixarImagePlugin.PixarImageFile attribute), 134
format_description

- (*PIL.PngImagePlugin.PngImageFile* attribute), 135
- `format_description` (*PIL.PpmImagePlugin.PpmImageFile* attribute), 136
- `format_description` (*PIL.PsdImagePlugin.PsdImageFile* attribute), 136
- `format_description` (*PIL.SgiImagePlugin.SgiImageFile* attribute), 137
- `format_description` (*PIL.SpiderImagePlugin.SpiderImageFile* attribute), 137
- `format_description` (*PIL.SunImagePlugin.SunImageFile* attribute), 138
- `format_description` (*PIL.TgaImagePlugin.TgaImageFile* attribute), 138
- `format_description` (*PIL.TiffImagePlugin.TiffImageFile* attribute), 141
- `format_description` (*PIL.WebPImagePlugin.WebPImageFile* attribute), 141
- `format_description` (*PIL.WmfImagePlugin.WmfStubImageFile* attribute), 142
- `format_description` (*PIL.XbmImagePlugin.XbmImageFile* attribute), 142
- `format_description` (*PIL.XpmImagePlugin.XpmImageFile* attribute), 142
- `format_description` (*PIL.XVThumbImagePlugin.XVThumbImageFile* attribute), 142
- `FpxImageFile` (class in *PIL.FpxImagePlugin*), 127
- `frame()` (*PIL.IcoImagePlugin.IcoFile* method), 130
- `FreeTypeFont` (class in *PIL.ImageFont*), 96
- `from_v2()` (*PIL.TiffImagePlugin.ImageFileDirectory_v1* class method), 139
- `fromarray()` (in module *PIL.Image*), 49
- `frombuffer()` (in module *PIL.Image*), 50
- `frombytes()` (in module *PIL.Image*), 50
- `frombytes()` (*PIL.ImageWin.Dib* method), 111
- `fromstring()` (in module *PIL.Image*), 50
- `fromstring()` (*PIL.Image.Image* method), 62
- G**
- `GaussianBlur` (class in *PIL.ImageFilter*), 92
- `GbrImageFile` (class in *PIL.GbrImagePlugin*), 127
- `GdImageFile` (class in *PIL.GdImageFile*), 117
- `generate()` (*PIL.ImageFilter.Color3DLUT* class method), 92
- `get_command()` (*PIL.ImageShow.UnixViewer* method), 119
- `get_command()` (*PIL.ImageShow.Viewer* method), 119
- `get_command_ex()` (*PIL.ImageShow.DisplayViewer* method), 119
- `get_command_ex()` (*PIL.ImageShow.EogViewer* method), 119
- `get_command_ex()` (*PIL.ImageShow.XVViewer* method), 119
- `get_format()` (*PIL.ImageShow.Viewer* method), 119
- `get_interlace()` (in module *PIL.GifImagePlugin*), 128
- `get_sampling()` (in module *PIL.JpegImagePlugin*), 132
- `get_variation_axes()` (*PIL.ImageFont.FreeTypeFont* method), 96
- `get_variation_names()` (*PIL.ImageFont.FreeTypeFont* method), 96
- `getbands()` (*PIL.Image.Image* method), 54
- `getbbox()` (*PIL.Image.Image* method), 54
- `getbbox()` (*PIL.ImagePath.PIL.ImagePath.Path* method), 108
- `getchannel()` (*PIL.Image.Image* method), 60
- `getchunks()` (in module *PIL.PngImagePlugin*), 134
- `getcolor()` (in module *PIL.ImageColor*), 67
- `getcolor()` (*PIL.ImagePalette.ImagePalette* method), 107
- `getcolors()` (*PIL.Image.Image* method), 55
- `getdata()` (in module *PIL.GifImagePlugin*), 128
- `getdata()` (*PIL.Image.Image* method), 55
- `getdata()` (*PIL.ImagePalette.ImagePalette* method), 107
- `getdata()` (*PIL.ImageTransform.Transform* method), 121
- `getdraw()` (*PIL.ImageDraw.PIL.ImageDraw* method), 87
- `getentryindex()` (*PIL.IcoImagePlugin.IcoFile* method), 130
- `getexif()` (*PIL.PngImagePlugin.PngImageFile* method), 135
- `getextrema()` (*PIL.Image.Image* method), 55
- `getfont()` (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw* method), 83
- `getheader()` (in module *PIL.GifImagePlugin*), 128
- `getimage()` (*PIL.IcnsImagePlugin.IcnsFile* method), 129
- `getimage()` (*PIL.IcoImagePlugin.IcoFile* method), 130
- `getint()` (*PIL.IptcImagePlugin.IptcImageFile* method), 131
- `getiptcinfo()` (in module *PIL.IptcImagePlugin*),

131
 getmask() (*PIL.ImageFont.FreeTypeFont* method), 96
 getmask() (*PIL.ImageFont.ImageFont* method), 95
 getmask2() (*PIL.ImageFont.FreeTypeFont* method), 97
 getmetrics() (*PIL.ImageFont.FreeTypeFont* method), 97
 getname() (*PIL.ImageFont.FreeTypeFont* method), 98
 getoffset() (*PIL.ImageFont.FreeTypeFont* method), 98
 getpalette() (*PIL.GimpGradientFile.GradientFile* method), 118
 getpalette() (*PIL.GimpPaletteFile.GimpPaletteFile* method), 118
 getpalette() (*PIL.Image.Image* method), 55
 getpalette() (*PIL.PaletteFile.PaletteFile* method), 122
 getpixel() (*PIL.Image.Image* method), 55
 getrgb() (in module *PIL.ImageColor*), 67
 getsize() (*PIL.ImageFont.FreeTypeFont* method), 98
 getsize() (*PIL.ImageFont.ImageFont* method), 96
 getsize_multiline() (*PIL.ImageFont.FreeTypeFont* method), 98
 Ghostscript() (in module *PIL.EpsImagePlugin*), 126
 GifImageFile (class in *PIL.GifImagePlugin*), 127
 GimpGradientFile (class in *PIL.GimpGradientFile*), 118
 GimpPaletteFile (class in *PIL.GimpPaletteFile*), 118
 global_palette (*PIL.GifImagePlugin.GifImageFile* attribute), 127
 goToEnd() (*PIL.TiffImagePlugin.AppendingTiffWriter* method), 138
 gradient (*PIL.GimpGradientFile.GradientFile* attribute), 118
 GradientFile (class in *PIL.GimpGradientFile*), 118
 grayscale() (in module *PIL.ImageOps*), 105
 green_colorant (*PIL.ImageCms.CmsProfile* attribute), 78
 green_primary (*PIL.ImageCms.CmsProfile* attribute), 79
 GribStubImageFile (class in *PIL.GribStubImagePlugin*), 128

H

hard_light() (in module *PIL.ImageChops*), 65
 has_ghostscript() (in module *PIL.EpsImagePlugin*), 126
 HDC (class in *PIL.ImageWin*), 112
 HDF5StubImageFile (class in *PIL.Hdf5StubImagePlugin*), 129
 header_flags (*PIL.ImageCms.CmsProfile* attribute), 77

header_manufacturer (*PIL.ImageCms.CmsProfile* attribute), 77
 header_model (*PIL.ImageCms.CmsProfile* attribute), 77
 height (in module *PIL.Image*), 63
 height() (*PIL.ImageTk.BitmapImage* method), 110
 height() (*PIL.ImageTk.PhotoImage* method), 110
 histogram() (*PIL.Image.Image* method), 55
 HWND (class in *PIL.ImageWin*), 112

I

i() (in module *PIL.IptcImagePlugin*), 131
 i16be() (in module *PIL._binary*), 123
 i16le() (in module *PIL._binary*), 123
 i32be() (in module *PIL._binary*), 124
 i32le() (in module *PIL._binary*), 124
 i8() (in module *PIL._binary*), 124
 icc_version (*PIL.ImageCms.CmsProfile* attribute), 76
 IcnsFile (class in *PIL.IcnsImagePlugin*), 129
 IcnsImageFile (class in *PIL.IcnsImagePlugin*), 129
 IcoFile (class in *PIL.IcoImagePlugin*), 130
 IcoImageFile (class in *PIL.IcoImagePlugin*), 130
 IFDRational (class in *PIL.TiffImagePlugin*), 139
 Image (class in *PIL.Image*), 52
 image() (*PIL.PSDraw.PSDraw* method), 114
 ImageFileDirectory (in module *PIL.TiffImagePlugin*), 139
 ImageFileDirectory_v1 (class in *PIL.TiffImagePlugin*), 139
 ImageFileDirectory_v2 (class in *PIL.TiffImagePlugin*), 139
 ImageFont (class in *PIL.ImageFont*), 95
 ImagePalette (class in *PIL.ImagePalette*), 106
 ImageQt.ImageQt (class in *PIL.ImageQt*), 108
 ImImageFile (class in *PIL.ImImagePlugin*), 130
 ImtImageFile (class in *PIL.ImtImagePlugin*), 131
 info (in module *PIL.Image*), 63
 init() (*PIL.ImageFile.PyDecoder* method), 90
 int() (built-in function), 101
 intent_supported (*PIL.ImageCms.CmsProfile* attribute), 80
 invert() (in module *PIL.ImageChops*), 64
 invert() (in module *PIL.ImageOps*), 106
 IptcImageFile (class in *PIL.IptcImagePlugin*), 131
 is_animated (*PIL.DcxImagePlugin.DcxImageFile* attribute), 125
 is_animated (*PIL.FliImagePlugin.FliImageFile* attribute), 126
 is_animated (*PIL.GifImagePlugin.GifImageFile* attribute), 127
 is_animated (*PIL.ImImagePlugin.ImImageFile* attribute), 130

- is_animated (*PIL.MicImagePlugin.MicImageFile* attribute), 133
- is_animated (*PIL.PsdImagePlugin.PsdImageFile* attribute), 136
- is_animated (*PIL.SpiderImagePlugin.SpiderImageFile* attribute), 137
- is_animated (*PIL.TiffImagePlugin.TiffImageFile* attribute), 141
- is_animated (*PIL.WebPImagePlugin.WebPImageFile* attribute), 141
- is_cid() (in module *PIL.PngImagePlugin*), 134
- is_intent_supported() (*PIL.ImageCms.CmsProfile* method), 80
- is_matrix_shaper (*PIL.ImageCms.CmsProfile* attribute), 79
- isatty() (*PIL.ContainerIO.ContainerIO* method), 116
- isInt() (in module *PIL.SpiderImagePlugin*), 137
- isSpiderHeader() (in module *PIL.SpiderImagePlugin*), 137
- isSpiderImage() (in module *PIL.SpiderImagePlugin*), 137
- Iterator (class in *PIL.ImageSequence*), 109
- itersizes() (*PIL.IcnsImagePlugin.IcnsFile* method), 129
- iTXXt (class in *PIL.PngImagePlugin*), 122
- ## J
- JPEG (*PIL.BmpImagePlugin.BmpImageFile* attribute), 124
- Jpeg2KImageFile (class in *PIL.Jpeg2KImagePlugin*), 132
- jpeg_factory() (in module *PIL.JpegImagePlugin*), 132
- JpegImageFile (class in *PIL.JpegImagePlugin*), 131
- ## K
- k (*PIL.BmpImagePlugin.BmpImageFile* attribute), 125
- Kernel (class in *PIL.ImageFilter*), 93
- ## L
- legacy_api (*PIL.TiffImagePlugin.ImageFileDirectory_v2* attribute), 140
- lighter() (in module *PIL.ImageChops*), 65
- limit_rational() (*PIL.TiffImagePlugin.IFDRational* method), 139
- line() (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw* method), 83
- line() (*PIL.ImageDraw2.Draw* method), 118
- line() (*PIL.PSDraw.PSDraw* method), 114
- linear() (in module *PIL.GimpGradientFile*), 118
- load() (in module *PIL.ImageFont*), 94
- load() (*PIL.EpsImagePlugin.EpsImageFile* method), 126
- load() (*PIL.FpxImagePlugin.FpxImageFile* method), 127
- load() (*PIL.GbrImagePlugin.GbrImageFile* method), 127
- load() (*PIL.IcnsImagePlugin.IcnsImageFile* method), 129
- load() (*PIL.IcoImagePlugin.IcoImageFile* method), 130
- load() (*PIL.Image.Image* method), 62
- load() (*PIL.IptcImagePlugin.IptcImageFile* method), 131
- load() (*PIL.Jpeg2KImagePlugin.Jpeg2KImageFile* method), 132
- load() (*PIL.TiffImagePlugin.ImageFileDirectory_v2* method), 140
- load() (*PIL.TiffImagePlugin.TiffImageFile* method), 141
- load() (*PIL.WebPImagePlugin.WebPImageFile* method), 141
- load() (*PIL.WmfImagePlugin.WmfStubImageFile* method), 142
- load_byte() (*PIL.TiffImagePlugin.ImageFileDirectory_v2* method), 140
- load_default() (in module *PIL.ImageFont*), 95
- load_djpeg() (*PIL.JpegImagePlugin.JpegImageFile* method), 132
- load_double() (*PIL.TiffImagePlugin.ImageFileDirectory_v2* method), 140
- load_end() (*PIL.GifImagePlugin.GifImageFile* method), 127
- load_end() (*PIL.PcdImagePlugin.PcdImageFile* method), 134
- load_end() (*PIL.PngImagePlugin.PngImageFile* method), 135
- load_end() (*PIL.TiffImagePlugin.TiffImageFile* method), 141
- load_float() (*PIL.TiffImagePlugin.ImageFileDirectory_v2* method), 140
- load_long() (*PIL.TiffImagePlugin.ImageFileDirectory_v2* method), 140
- load_path() (in module *PIL.ImageFont*), 94
- load_prepare() (*PIL.PngImagePlugin.PngImageFile* method), 135
- load_prepare() (*PIL.PsdImagePlugin.PsdImageFile* method), 136
- load_rational() (*PIL.TiffImagePlugin.ImageFileDirectory_v2* method), 140
- load_read() (*PIL.JpegImagePlugin.JpegImageFile* method), 132
- load_read() (*PIL.PngImagePlugin.PngImageFile* method), 135
- load_read() (*PIL.XpmlImagePlugin.XpmlImageFile* method), 142
- load_seek() (*PIL.EpsImagePlugin.EpsImageFile* method), 126

- method), 126
- load_seek() (PIL.IcoImagePlugin.IcoImageFile method), 130
- load_short() (PIL.TiffImagePlugin.ImageFileDirectory_v2 method), 140
- load_signed_byte() (PIL.TiffImagePlugin.ImageFileDirectory_v2 method), 140
- load_signed_long() (PIL.TiffImagePlugin.ImageFileDirectory_v2 method), 140
- load_signed_rational() (PIL.TiffImagePlugin.ImageFileDirectory_v2 method), 140
- load_signed_short() (PIL.TiffImagePlugin.ImageFileDirectory_v2 method), 140
- load_string() (PIL.TiffImagePlugin.ImageFileDirectory_v2 method), 140
- load_undefined() (PIL.TiffImagePlugin.ImageFileDirectory_v2 method), 140
- loadImageSeries() (in module PIL.SpiderImagePlugin), 138
- logical_and() (in module PIL.ImageChops), 65
- logical_or() (in module PIL.ImageChops), 65
- logical_xor() (in module PIL.ImageChops), 65
- lookup() (in module PIL.TiffTags), 113
- luminance (PIL.ImageCms.CmsProfile attribute), 78
- ## M
- makeSpiderHeader() (in module PIL.SpiderImagePlugin), 138
- manufacturer (PIL.ImageCms.CmsProfile attribute), 77
- map() (PIL.ImagePath.PIL.ImagePath.Path method), 108
- max() (built-in function), 101
- MaxFilter (class in PIL.ImageFilter), 93
- McIDASImageFile (class in PIL.McIDASImagePlugin), 133
- mean (PIL.ImageStat.PIL.ImageStat.Stat attribute), 109
- media_black_point (PIL.ImageCms.CmsProfile attribute), 79
- media_white_point_temperature (PIL.ImageCms.CmsProfile attribute), 79
- median (PIL.ImageStat.PIL.ImageStat.Stat attribute), 109
- MedianFilter (class in PIL.ImageFilter), 93
- merge() (in module PIL.Image), 49
- MeshTransform (class in PIL.ImageTransform), 120
- method (PIL.ImageTransform.AffineTransform attribute), 120
- method (PIL.ImageTransform.ExtentTransform attribute), 120
- method (PIL.ImageTransform.MeshTransform attribute), 120
- method (PIL.ImageTransform.QuadTransform attribute), 121
- MicImageFile (class in PIL.MicImagePlugin), 133
- min() (built-in function), 101
- MinFilter (class in PIL.ImageFilter), 93
- mirror() (in module PIL.ImageOps), 106
- mode (in module PIL.Image), 63
- mode_map (PIL.EpsImagePlugin.EpsImageFile attribute), 126
- ModeFilter (class in PIL.ImageFilter), 93
- model (PIL.ImageCms.CmsProfile attribute), 77
- MpegImageFile (class in PIL.MpegImagePlugin), 133
- MspDecoder (class in PIL.MspImagePlugin), 133
- MspImageFile (class in PIL.MspImagePlugin), 133
- multiline_text() (PIL.ImageDraw.PIL.ImageDraw.ImageDraw method), 86
- multiline_textsize() (PIL.ImageDraw.PIL.ImageDraw.ImageDraw method), 87
- multiply() (in module PIL.ImageChops), 65
- ## N
- n_frames (PIL.DcxImagePlugin.DcxImageFile attribute), 125
- n_frames (PIL.FliImagePlugin.FliImageFile attribute), 127
- n_frames (PIL.GifImagePlugin.GifImageFile attribute), 127
- n_frames (PIL.ImImagePlugin.ImImageFile attribute), 130
- n_frames (PIL.MicImagePlugin.MicImageFile attribute), 133
- n_frames (PIL.PsdImagePlugin.PsdImageFile attribute), 136
- n_frames (PIL.SpiderImagePlugin.SpiderImageFile attribute), 137
- n_frames (PIL.TiffImagePlugin.TiffImageFile attribute), 141
- n_frames (PIL.WebPImagePlugin.WebPImageFile attribute), 141
- name (PIL.PcfFontFile.PcfFontFile attribute), 122
- named() (PIL.TiffImagePlugin.ImageFileDirectory_v2 method), 140
- new() (in module PIL.Image), 49
- newFrame() (PIL.TiffImagePlugin.AppendingTiffWriter method), 138
- next() (PIL.MpegImagePlugin.BitStream method), 133
- nextheader() (in module PIL.IcnsImagePlugin), 129
- number() (in module PIL.ImImagePlugin), 131
- numerator (PIL.TiffImagePlugin.IFDRational attribute), 139

O

o16be () (in module *PIL._binary*), 124
 o16le () (in module *PIL._binary*), 124
 o32be () (in module *PIL._binary*), 124
 o32le () (in module *PIL._binary*), 124
 o8 () (in module *PIL._binary*), 124
 offset (*PIL.TiffImagePlugin.ImageFileDirectory_v2* attribute), 140
 offset () (*PIL.Image* method), 56
 offset () (*PIL.ImageChops.PIL.ImageChops* method), 66
 open () (in module *PIL.GdImageFile*), 117
 open () (in module *PIL.Image*), 48
 open () (in module *PIL.WallImageFile*), 123
 options (*PIL.ImageShow.UnixViewer* attribute), 119
 options (*PIL.ImageShow.Viewer* attribute), 119
 overlay () (in module *PIL.ImageChops*), 66

P

pad () (in module *PIL.ImageOps*), 104
 palette (in module *PIL.Image*), 63
 PaletteFile (class in *PIL.PaletteFile*), 122
 Parser (class in *PIL.ImageFile*), 90
 paste () (*PIL.Image* method), 56
 paste () (*PIL.ImageTk.PhotoImage* method), 110
 paste () (*PIL.ImageWin.Dib* method), 111
 PcdImageFile (class in *PIL.PcdImagePlugin*), 134
 PcfFontFile (class in *PIL.PcfFontFile*), 122
 pcs (*PIL.ImageCms.CmsProfile* attribute), 80
 PcxImageFile (class in *PIL.PcxImagePlugin*), 134
 peek () (*PIL.MpegImagePlugin.BitStream* method), 133
 Pen (class in *PIL.ImageDraw2*), 119
 perceptual_rendering_intent_gamut (*PIL.ImageCms.CmsProfile* attribute), 78
 PhotoImage (class in *PIL.ImageTk*), 110
 pieslice () (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw* method), 84
 pieslice () (*PIL.ImageDraw2.Draw* method), 118
 PIL._binary (module), 123
 PIL.BdfFontFile (module), 116
 PIL.BmpImagePlugin (module), 124
 PIL.BufrStubImagePlugin (module), 125
 PIL.ContainerIO (module), 116
 PIL.CurImagePlugin (module), 125
 PIL.DcxImagePlugin (module), 125
 PIL.EpsImagePlugin (module), 126
 PIL.ExifTags (module), 112
 PIL.ExifTags.GPSTAGS (class in *PIL.ExifTags*), 112
 PIL.ExifTags.TAGS (class in *PIL.ExifTags*), 112
 PIL.FitsStubImagePlugin (module), 126
 PIL.FliImagePlugin (module), 126
 PIL.FontFile (module), 117
 PIL.FpxImagePlugin (module), 127
 PIL.GbrImagePlugin (module), 127
 PIL.GdImageFile (module), 117
 PIL.GifImagePlugin (module), 127
 PIL.GimpGradientFile (module), 118
 PIL.GimpPaletteFile (module), 118
 PIL.GribStubImagePlugin (module), 128
 PIL.Hdf5StubImagePlugin (module), 129
 PIL.IcnsImagePlugin (module), 129
 PIL.IcoImagePlugin (module), 130
 PIL.Image (module), 47
 PIL.ImageChops (module), 63
 PIL.ImageCms (module), 67
 PIL.ImageColor (module), 66
 PIL.ImageDraw (module), 81
 PIL.ImageDraw.Draw (class in *PIL.ImageDraw*), 82
 PIL.ImageDraw2 (module), 118
 PIL.ImageEnhance (module), 88
 PIL.ImageEnhance._Enhance (class in *PIL.ImageEnhance*), 88
 PIL.ImageEnhance.Brightness (class in *PIL.ImageEnhance*), 89
 PIL.ImageEnhance.Color (class in *PIL.ImageEnhance*), 89
 PIL.ImageEnhance.Contrast (class in *PIL.ImageEnhance*), 89
 PIL.ImageEnhance.Sharpness (class in *PIL.ImageEnhance*), 89
 PIL.ImageFile (module), 89
 PIL.ImageFilter (module), 91
 PIL.ImageFont (module), 93
 PIL.ImageGrab (module), 99
 PIL.ImageGrab.grab () (in module *PIL.ImageGrab*), 99
 PIL.ImageGrab.grabclipboard () (in module *PIL.ImageGrab*), 100
 PIL.ImageMath (module), 100
 PIL.ImageMorph (module), 101
 PIL.ImageOps (module), 103
 PIL.ImagePalette (module), 106
 PIL.ImagePath (module), 107
 PIL.ImagePath.Path (class in *PIL.ImagePath*), 107
 PIL.ImageQt (module), 108
 PIL.ImageSequence (module), 108
 PIL.ImageShow (module), 119
 PIL.ImageStat (module), 109
 PIL.ImageStat.Stat (class in *PIL.ImageStat*), 109
 PIL.ImageTk (module), 110
 PIL.ImageTransform (module), 120
 PIL.ImageWin (module), 111
 PIL.ImImagePlugin (module), 130
 PIL.ImtImagePlugin (module), 131
 PIL.IptcImagePlugin (module), 131
 PIL.Jpeg2KImagePlugin (module), 132
 PIL.JpegImagePlugin (module), 131

- PIL.JpegPresets (module), 121
 - PIL.McIDASImagePlugin (module), 133
 - PIL.MicImagePlugin (module), 133
 - PIL.MpegImagePlugin (module), 133
 - PIL.MspImagePlugin (module), 133
 - PIL.PaletteFile (module), 122
 - PIL.PalmImagePlugin (module), 134
 - PIL.PcdImagePlugin (module), 134
 - PIL.PcfFontFile (module), 122
 - PIL.PcxImagePlugin (module), 134
 - PIL.PdfImagePlugin (module), 134
 - PIL.PixarImagePlugin (module), 134
 - PIL.PngImagePlugin (module), 134
 - PIL.PpmImagePlugin (module), 136
 - PIL.PsdImagePlugin (module), 136
 - PIL.PSDraw (module), 113
 - PIL.PyAccess (module), 115
 - PIL.SgiImagePlugin (module), 137
 - PIL.SpiderImagePlugin (module), 137
 - PIL.SunImagePlugin (module), 138
 - PIL.TarIO (module), 123
 - PIL.TgaImagePlugin (module), 138
 - PIL.TiffImagePlugin (module), 138
 - PIL.TiffTags (module), 112
 - PIL.WalImageFile (module), 123
 - PIL.WebPImagePlugin (module), 141
 - PIL.WmfImagePlugin (module), 142
 - PIL.XbmImagePlugin (module), 142
 - PIL.XpmImagePlugin (module), 142
 - PIL.XVThumbImagePlugin (module), 142
 - PixarImageFile (class in PIL.PixarImagePlugin), 134
 - PixelAccess (built-in class), 115
 - PNG (PIL.BmpImagePlugin.BmpImageFile attribute), 124
 - PngImageFile (class in PIL.PngImagePlugin), 135
 - PngInfo (class in PIL.PngImagePlugin), 122
 - PngStream (class in PIL.PngImagePlugin), 135
 - point () (PIL.Image.Image method), 56
 - point () (PIL.ImageDraw.PIL.ImageDraw.ImageDraw method), 84
 - polygon () (PIL.ImageDraw.PIL.ImageDraw.ImageDraw method), 84
 - polygon () (PIL.ImageDraw2.Draw method), 118
 - posterize () (in module PIL.ImageOps), 106
 - PpmImageFile (class in PIL.PpmImagePlugin), 136
 - prefix (PIL.TiffImagePlugin.ImageFileDirectory_v2 attribute), 140
 - product_copyright (PIL.ImageCms.CmsProfile attribute), 80
 - product_desc (PIL.ImageCms.CmsProfile attribute), 80
 - product_description (PIL.ImageCms.CmsProfile attribute), 80
 - product_manufacturer (PIL.ImageCms.CmsProfile attribute), 80
 - product_model (PIL.ImageCms.CmsProfile attribute), 80
 - profile_description (PIL.ImageCms.CmsProfile attribute), 77
 - profile_id (PIL.ImageCms.CmsProfile attribute), 77
 - PsdImageFile (class in PIL.PsdImagePlugin), 136
 - PSDraw (class in PIL.PSDraw), 113
 - PSFile (class in PIL.EpsImagePlugin), 126
 - push () (PIL.PngImagePlugin.ChunkStream method), 135
 - putalpha () (PIL.Image.Image method), 56
 - putchunk () (in module PIL.PngImagePlugin), 134
 - putdata () (PIL.Image.Image method), 56
 - puti16 () (in module PIL.FontFile), 117
 - putpalette () (PIL.Image.Image method), 57
 - putpixel () (PIL.Image.Image method), 57
 - PyDecoder (class in PIL.ImageFile), 90
- ## Q
- QuadTransform (class in PIL.ImageTransform), 120
 - quantize () (PIL.Image.Image method), 57
 - query_palette () (PIL.ImageWin.Dib method), 112
- ## R
- RankFilter (class in PIL.ImageFilter), 93
 - RAW (PIL.BmpImagePlugin.BmpImageFile attribute), 124
 - rawmode (PIL.GimpPaletteFile.GimpPaletteFile attribute), 118
 - rawmode (PIL.PaletteFile.PaletteFile attribute), 122
 - read () (PIL.ContainerIO.ContainerIO method), 116
 - read () (PIL.MpegImagePlugin.BitStream method), 133
 - read () (PIL.PngImagePlugin.ChunkStream method), 135
 - read_32 () (in module PIL.IcnsImagePlugin), 129
 - read_32t () (in module PIL.IcnsImagePlugin), 129
 - read_mk () (in module PIL.IcnsImagePlugin), 129
 - read_png_or_jpeg2000 () (in module PIL.IcnsImagePlugin), 129
 - readline () (PIL.ContainerIO.ContainerIO method), 116
 - readline () (PIL.EpsImagePlugin.PSFile method), 126
 - readlines () (PIL.ContainerIO.ContainerIO method), 117
 - readLong () (PIL.TiffImagePlugin.AppendingTiffWriter method), 138
 - readShort () (PIL.TiffImagePlugin.AppendingTiffWriter method), 138
 - rectangle () (PIL.ImageDraw.PIL.ImageDraw.ImageDraw method), 85
 - rectangle () (PIL.ImageDraw2.Draw method), 118

- rectangle() (*PIL.PSDraw.PSDraw method*), 114
- red_colorant (*PIL.ImageCms.CmsProfile attribute*), 78
- red_primary (*PIL.ImageCms.CmsProfile attribute*), 79
- reduce (*PIL.Jpeg2KImagePlugin.Jpeg2KImageFile attribute*), 132
- register() (*in module PIL.ImageShow*), 119
- register_decoder() (*in module PIL.Image*), 51
- register_encoder() (*in module PIL.Image*), 52
- register_extension() (*in module PIL.Image*), 52
- register_handler() (*in module PIL.BufrStubImagePlugin*), 125
- register_handler() (*in module PIL.FitsStubImagePlugin*), 126
- register_handler() (*in module PIL.GribStubImagePlugin*), 128
- register_handler() (*in module PIL.Hdf5StubImagePlugin*), 129
- register_handler() (*in module PIL.WmfImagePlugin*), 142
- register_mime() (*in module PIL.Image*), 51
- register_open() (*in module PIL.Image*), 51
- register_save() (*in module PIL.Image*), 51
- remap_palette() (*PIL.Image.Image method*), 58
- render() (*PIL.ImageDraw2.Draw method*), 118
- rendering_intent (*PIL.ImageCms.CmsProfile attribute*), 77
- reset() (*PIL.ImageFile.Parser method*), 90
- reset() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 140
- resize() (*PIL.Image.Image method*), 57
- rewind() (*PIL.PngImagePlugin.PngStream method*), 136
- rewriteLastLong() (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 138
- rewriteLastShort() (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 138
- rewriteLastShortToLong() (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 138
- RLE4 (*PIL.BmpImagePlugin.BmpImageFile attribute*), 124
- RLE8 (*PIL.BmpImagePlugin.BmpImageFile attribute*), 124
- rms (*PIL.ImageStat.PIL.ImageStat.Stat attribute*), 110
- rotate() (*PIL.Image.Image method*), 58
- save() (*PIL.Image.Image method*), 59
- save() (*PIL.ImagePalette.ImagePalette method*), 107
- save() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 140
- save_image() (*PIL.ImageShow.Viewer method*), 119
- save_rewind() (*PIL.PngImagePlugin.PngStream method*), 136
- scale() (*in module PIL.ImageOps*), 104
- screen() (*in module PIL.ImageChops*), 66
- screening_description (*PIL.ImageCms.CmsProfile attribute*), 79
- seek() (*PIL.ContainerIO.ContainerIO method*), 117
- seek() (*PIL.DcxImagePlugin.DcxImageFile method*), 125
- seek() (*PIL.EpsImagePlugin.PSFile method*), 126
- seek() (*PIL.FliImagePlugin.FliImageFile method*), 127
- seek() (*PIL.GifImagePlugin.GifImageFile method*), 128
- seek() (*PIL.Image.Image method*), 59
- seek() (*PIL.ImImagePlugin.ImImageFile method*), 130
- seek() (*PIL.MicImagePlugin.MicImageFile method*), 133
- seek() (*PIL.PngImagePlugin.PngImageFile method*), 135
- seek() (*PIL.PsdImagePlugin.PsdImageFile method*), 136
- seek() (*PIL.SpiderImagePlugin.SpiderImageFile method*), 137
- seek() (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 138
- seek() (*PIL.TiffImagePlugin.TiffImageFile method*), 141
- seek() (*PIL.WebPImagePlugin.WebPImageFile method*), 141
- set_as_raw() (*PIL.ImageFile.PyDecoder method*), 90
- set_variation_by_axes() (*PIL.ImageFont.FreeTypeFont method*), 99
- set_variation_by_name() (*PIL.ImageFont.FreeTypeFont method*), 99
- setEndian() (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 138
- setfd() (*PIL.ImageFile.PyDecoder method*), 90
- setfont() (*PIL.PSDraw.PSDraw method*), 114
- setimage() (*PIL.ImageFile.PyDecoder method*), 91
- settransform() (*PIL.ImageDraw2.Draw method*), 118
- setup() (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 138
- SGI16Decoder (*class in PIL.SgiImagePlugin*), 137
- SgiImageFile (*class in PIL.SgiImagePlugin*), 137
- shape() (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw method*), 85

S

- saturation_rendering_intent_gamut (*PIL.ImageCms.CmsProfile attribute*), 79
- save() (*PIL.FontFile.FontFile method*), 117

- show () (in module *PIL.ImageShow*), 119
 show () (*PIL.Image.Image* method), 59
 show () (*PIL.ImageShow.Viewer* method), 119
 show_file () (*PIL.ImageShow.UnixViewer* method), 119
 show_file () (*PIL.ImageShow.Viewer* method), 119
 show_image () (*PIL.ImageShow.Viewer* method), 119
 si16le () (in module *PIL._binary*), 124
 si32le () (in module *PIL._binary*), 124
 sine () (in module *PIL.GimpGradientFile*), 118
 size (in module *PIL.Image*), 63
 size (*PIL.IcnsImagePlugin.IcnsImageFile* attribute), 129
 size (*PIL.IcoImagePlugin.IcoImageFile* attribute), 130
 SIZES (*PIL.IcnsImagePlugin.IcnsFile* attribute), 129
 sizes () (*PIL.IcoImagePlugin.IcoFile* method), 130
 Skip () (in module *PIL.JpegImagePlugin*), 132
 skip () (*PIL.MpegImagePlugin.BitStream* method), 133
 skipIFDs () (*PIL.TiffImagePlugin.AppendingTiffWriter* method), 138
 SOF () (in module *PIL.JpegImagePlugin*), 132
 soft_light () (in module *PIL.ImageChops*), 65
 solarize () (in module *PIL.ImageOps*), 106
 sphere_decreasing () (in module *PIL.GimpGradientFile*), 118
 sphere_increasing () (in module *PIL.GimpGradientFile*), 118
 SpiderImageFile (class in *PIL.SpiderImagePlugin*), 137
 split () (*PIL.Image.Image* method), 60
 stddev (*PIL.ImageStat.PIL.ImageStat.Stat* attribute), 110
 subtract () (in module *PIL.ImageChops*), 66
 subtract_modulo () (in module *PIL.ImageChops*), 66
 sum (*PIL.ImageStat.PIL.ImageStat.Stat* attribute), 109
 sum2 (*PIL.ImageStat.PIL.ImageStat.Stat* attribute), 109
 SunImageFile (class in *PIL.SunImagePlugin*), 138
 sz () (in module *PIL.PcfFontFile*), 122
- ## T
- tagdata (*PIL.TiffImagePlugin.ImageFileDirectory_v1* attribute), 139
 TagInfo (class in *PIL.TiffTags*), 113
 Tags (*PIL.TiffImagePlugin.AppendingTiffWriter* attribute), 138
 tags (*PIL.TiffImagePlugin.ImageFileDirectory_v1* attribute), 139
 TAGS (*PIL.TiffTags.PIL.TiffTags* attribute), 113
 TAGS_V2 (*PIL.TiffTags.PIL.TiffTags* attribute), 113
 target (*PIL.ImageCms.CmsProfile* attribute), 77
 TarIO (class in *PIL.TarIO*), 123
 technology (*PIL.ImageCms.CmsProfile* attribute), 79
 tell () (*PIL.ContainerIO.ContainerIO* method), 117
 tell () (*PIL.DcxImagePlugin.DcxImageFile* method), 126
 tell () (*PIL.FliImagePlugin.FliImageFile* method), 127
 tell () (*PIL.GifImagePlugin.GifImageFile* method), 128
 tell () (*PIL.Image.Image* method), 60
 tell () (*PIL.ImImagePlugin.ImImageFile* method), 131
 tell () (*PIL.MicImagePlugin.MicImageFile* method), 133
 tell () (*PIL.PngImagePlugin.PngImageFile* method), 135
 tell () (*PIL.PsdImagePlugin.PsdImageFile* method), 137
 tell () (*PIL.SpiderImagePlugin.SpiderImageFile* method), 137
 tell () (*PIL.TiffImagePlugin.AppendingTiffWriter* method), 138
 tell () (*PIL.TiffImagePlugin.TiffImageFile* method), 141
 tell () (*PIL.WebPImagePlugin.WebPImageFile* method), 142
 text (*PIL.PngImagePlugin.PngImageFile* attribute), 135
 text () (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw* method), 85
 text () (*PIL.ImageDraw2.Draw* method), 118
 text () (*PIL.PSDraw.PSDraw* method), 114
 textsize () (*PIL.ImageDraw.PIL.ImageDraw.ImageDraw* method), 86
 textsize () (*PIL.ImageDraw2.Draw* method), 118
 TgaImageFile (class in *PIL.TgaImagePlugin*), 138
 thumbnail () (*PIL.Image.Image* method), 60
 TiffImageFile (class in *PIL.TiffImagePlugin*), 141
 tkPhotoImage () (*PIL.SpiderImagePlugin.SpiderImageFile* method), 137
 to_v2 () (*PIL.TiffImagePlugin.ImageFileDirectory_v1* method), 139
 tobitmap () (*PIL.Image.Image* method), 60
 tobytes () (*PIL.Image.Image* method), 61
 tobytes () (*PIL.ImagePalette.ImagePalette* method), 107
 tobytes () (*PIL.ImageWin.Dib* method), 112
 tobytes () (*PIL.TiffImagePlugin.ImageFileDirectory_v2* method), 140
 tolist () (*PIL.ImagePath.PIL.ImagePath.Path* method), 108
 tostring () (*PIL.Image.Image* method), 61
 tostring () (*PIL.ImagePalette.ImagePalette* method), 107
 Transform (class in *PIL.ImageTransform*), 121
 transform () (*PIL.Image.Image* method), 61
 transform () (*PIL.ImageFilter.Color3DLUT* method), 92

- transform() (*PIL.ImagePath.PIL.ImagePath.Path method*), 108
- transform() (*PIL.ImageTransform.Transform method*), 121
- transpose() (*PIL.Image.Image method*), 62
- TransposedFont (*class in PIL.ImageFont*), 99
- truetype() (*in module PIL.ImageFont*), 94
- TYPES (*PIL.TiffTags.PIL.TiffTags attribute*), 113
- ## U
- UnixViewer (*class in PIL.ImageShow*), 119
- UnsharpMask (*class in PIL.ImageFilter*), 93
- ## V
- v (*PIL.BmpImagePlugin.BmpImageFile attribute*), 125
- var (*PIL.ImageStat.PIL.ImageStat.Stat attribute*), 110
- verify() (*PIL.Image.Image method*), 62
- verify() (*PIL.PngImagePlugin.ChunkStream method*), 135
- verify() (*PIL.PngImagePlugin.PngImageFile method*), 135
- version (*PIL.ImageCms.CmsProfile attribute*), 76
- Viewer (*class in PIL.ImageShow*), 119
- viewing_condition (*PIL.ImageCms.CmsProfile attribute*), 79
- ## W
- WebPImageFile (*class in PIL.WebPImagePlugin*), 141
- width (*in module PIL.Image*), 63
- width() (*PIL.ImageTk.BitmapImage method*), 110
- width() (*PIL.ImageTk.PhotoImage method*), 111
- WmfStubImageFile (*class in PIL.WmfImagePlugin*), 142
- write() (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 139
- write_byte() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 140
- write_double() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_float() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_long() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_rational() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_short() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_signed_byte() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_signed_long() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_signed_rational() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_signed_short() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_string() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- write_undefined() (*PIL.TiffImagePlugin.ImageFileDirectory_v2 method*), 141
- writeLong() (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 139
- writeShort() (*PIL.TiffImagePlugin.AppendingTiffWriter method*), 139
- ## X
- XbmImageFile (*class in PIL.XbmImagePlugin*), 142
- xcolor_space (*PIL.ImageCms.CmsProfile attribute*), 76
- XpmImageFile (*class in PIL.XpmImagePlugin*), 142
- XVThumbImageFile (*class in PIL.XVThumbImagePlugin*), 142
- XVViewer (*class in PIL.ImageShow*), 119